

175-TP-511-003

HDF-EOS Interface Based on HDF5, Volume 2: Function Reference Guide

Technical Paper

May 2002

Prepared Under Contract NAS5-60000

RESPONSIBLE ENGINEER

<u>E M. Taaheri /s/</u>	<u>5/21/02</u>
Alex Muslimov, Abe Taaheri, Ray Milburn EOSDIS Core System Project	Date

SUBMITTED BY

<u>Darryl Arrington /s/</u>	<u>5/21/02</u>
Darryl Arrington, Manager Toolkit Larry Klein, Manager Toolkit EOSDIS Core System Project	Date

Raytheon Company
Upper Marlboro, Maryland

This page intentionally left blank.

Preface

This document is a Users Guide for HDF-EOS (Hierarchical Data Format - Earth Observing System) library tools. The version described in this document is HDF-EOS Version 5.1.2. The software is based on HDF5, a new version of HDF provided by NCSA. HDF5 is a complete rewrite of the earlier HDF4 version, containing a different data model and user interface. HDF-EOS V5.1.2 incorporates HDF5, and keeps the familiar HDF4-based interface. There are a few exceptions and these exceptions are described in this document. Note that the major functional difference is that Version 5.1.2 of the HDF-EOS library is a thread-safe.

HDF is the scientific data format standard selected by NASA as the baseline standard for EOS. This Users Guide accompanies Version 5.1.2 software, which is available to the user community on the EDHS1 server. This library is aimed at EOS data producers and consumers, who will develop their data into increasingly higher order products. These products range from calibrated Level 1 to Level 4 model data. The primary use of the HDF-EOS library will be to create structures for associating geolocation data with their associated science data. This association is specified by producers through use of the supplied library. Most EOS data products which have been identified, fall into categories of Point, Grid or Swath structures, the latter two of which are implemented in the current version of the library. Services based on geolocation information will be built on HDF-EOS structures. Producers of products not covered by these structures, e.g. non-geolocated data, can use the standard HDF libraries.

In the ECS (EOS Core System) production system, the HDF-EOS library will be used in conjunction with SDP (Science Data Processing) Toolkit software. The primary tools used in conjunction with HDF-EOS library will be those for metadata handling, process control and status message handling. Metadata tools will be used to write ECS inventory and granule specific metadata into HDF-EOS files, while the process control tools will be used to access physical file handles used by the HDF tools. (SDP Toolkit Users Guide for the ECS Project, November 2000, 333-CD-600-001).

HDF-EOS5 is an extension of NCSA (National Center for Supercomputing Applications) HDF5 and uses HDF5 library calls as an underlying basis. Version 5-1.4.1 of HDF5 is used. The library tools are written in the C language and a FORTRAN interface is provided. The current version contains software for creating, accessing and manipulating Grid, Point and Swath structures. This document includes overviews of the interfaces, and code examples. HE5View, the HDF-EOS viewing tool, has been revised to accommodate the current version of the library.

Note that HDF-EOS V2.X, a separate library based on HDF4, is also available. Both versions of HDF-EOS will be supported by ECS.

Technical Points of Contact within EOS are:

Larry Klein, larry@eos.hitc.com
David Wynne, davidw@eos.hitc.com
Alex Muslimov, amuslimo@eos.hitc.com

An email address has been provided for user help:
pgstlkit@eos.hitc.com

Any questions should be addressed to:

Data Management Office
The ECS Project Office
Raytheon Systems Company
1616 McCormick Drive
Upper Marlboro, MD 20774-5301

Abstract

This document will serve as the user's guide to the HDF-EOS file access library based on HDF5. HDF refers to the scientific data format standard selected by NASA as the baseline standard for EOS, and HDF-EOS refers to EOS conventions for using HDF. This document will provide information on the use of the three interfaces included in HDF-EOS – Point, Swath, and Grid – including overviews of the interfaces, and code examples. This document should be suitable for use by data producers and data users alike.

Keywords: HDF-EOS, HDF5, Metadata, Standard Data Format, Standard Data Product, Disk Format, Grid, Point, Swath, Projection, Array, Browse

This page intentionally left blank

Contents

Preface

Abstract

1. Introduction

1.1	Purpose	1-1
1.2	Organization	1-1
1.3	Point Data	1-1
1.3.1	The Point Data Interface.....	1-1
1.3.2	List of Point API Routines	1-2
1.4	Swath Data	1-3
1.4.1	The Swath Data Interface	1-3
1.4.2	List of Swath API Routines.....	1-3
1.5	Grid Data.....	1-5
1.5.1	The Grid Data Interface.....	1-6
1.5.2	List of Grid API Routines	1-6
1.6	GCTP Usage.....	1-8
1.6.1	GCTP Projection Codes	1-8
1.6.2	UTM Zone Codes.....	1-9
1.6.3	GCTP Spheroid Codes	1-9
1.6.4	GCTP Projection Parameters.....	1-10

2. Function Reference

2.1	Format	2-1
2.1.1	Point Interface Functions.....	2-1
2.1.2	Swath Interface Functions	2-45
2.1.3	Grid Interface Functions.....	2-143
2.1.4	HDF-EOS Utility Routines	2-219

List of Table

1-1. Summary of the Point Interface	1-2
1-2. Summary of the Swath Interface.....	1-4
1-3. Summary of the Grid Interface	1-6
1-4. Projection Transformation Package Projection Parameters.....	1-10

Abbreviations and Acronyms

1. Introduction

1.1 Purpose

The *HDF-EOS Software Reference Guide for the ECS Project* was prepared under the Earth Observing System Data and Information System (EOSDIS) Core System (ECS), Contract (NAS5-60000).

This software reference guide is intended for use by anyone who wishes to use the HDF-EOS library to create or read EOS data products. Users of this document will include EOS instrument team science software developers and data product designers, DAAC personnel, and end users of EOS data products such as scientists and researchers.

1.2 Organization

This paper is organized as follows:

- Section 1 Introduction - Presents Scope and Purpose of this document
- Section 2 Function Reference
- Abbreviations and Acronyms

1.3 Point Data

The Point (PT) interface consists of routines for storing, retrieving, and manipulating data in point data sets.

1.3.1 The Point Data Interface

All C routine names in the Point data interface have the prefix “HE5_PT” and the equivalent FORTRAN routine names are prefixed by “he5_pt.” The Point routines are classified into the following categories:

- *Access routines* initialize and terminate access to the Point interface and Point data sets (including opening and closing files).
- *Definition* routines allow the user to set key features of a Point data set.
- *Basic I/O* routines read and write data and metadata to a Point data set.
- *Index I/O* routines read and write information which links two tables in a Point data set.
- *Inquiry* routines return information about data contained in a Point data set.
- *Subset* routines allow reading of data from a specified geographic region.

1.3.2 List of Point API Routines

The Point function calls are listed in Table 1-1 and are described in detail in the Software Reference Guide that accompanies this document. The page number column in the following table refers to the Software Reference Guide.

Table 1-1. Summary of the Point Interface (1 of 2)

Category	Routine Name		Description	Pg. Nos.
	C	FORTRAN		
Access	HE5_Ptopen	he5_ptopen	Creates a new file or opens an existing one	2-30
	HE5_PTcreate	he5_ptcreate	Creates a new point data set and returns a handle	2-06
	HE5_PTattach	he5_ptattach	Attaches to an existing point data set	2-02
	HE5_PTdetach	he5_ptdetach	Releases a point data set and frees memory	2-14
	HE5_PTclose	he5_ptclose	Closes the HDF-EOS file and deactivates the point interface	2-05
Definition	HE5_PTdeflevel	he5_ptdeflevel	Defines a level within the point data set	2-07
	HE5_PTdeflinkage	he5_ptdeflinkage	Defines link field to use between two levels	2-13
	HE5_PTwritelevel	he5_ptwritelevel	Writes (appends) full records to a level	2-42
	HE5_PTreadlevel	he5_ptreadlevel	Reads data from the specified fields and records of a level	2-34
Basic I/O	HE5_PTupdatelevel	he5_ptupdatelevel	Updates the specified fields and records of a level	2-37
	HE5_PTwriteattr	he5_ptwriteattr	Creates or updates an attribute of the point data set	2-38
	HE5_PTwritegrpattr	he5_ptwritegrpattr	Writes/updates group attribute in a point	2-40
	HE5_PTwritelocattr	he5_ptwritelocattr	Write/updates local attribute in a point	2-43
	HE5_PTreadattr	he5_ptreadattr	Reads existing attribute of point data set	2-31
	HE5_PTreadgrpattr	he5_ptreadgrpattr	Reads group attribute from a point	2-32
	HE5_PTreadlocattr	he5_ptreadlocattr	Reads local attribute from a point	2-33
	HE5_PTnlevels	he5_ptnlevels	Returns the number of levels in a point data set	2-28
	HE5_PTnrecs	he5_ptnrecs	Returns the number of records in a level	2-39
	HE5_PTnfields	he5_ptnfields	Returns number of fields defined in a level	2-27
	HE5_PTlevelinfo	he5_ptlevelinfo	Returns information about a given level	2-25
	HE5_PTlevelindx	he5_ptlevelindx	Returns index number for a named level	2-24
Inquiry	HE5_PTbcklinkinfo	he5_ptbcklinkinfo	Returns link field to previous level	2-04
	HE5_PTfwdlinkinfo	he5_ptfwdlinkinfo	Returns link field to following level	2-15
	HE5_PTgetlevelname	he5_ptgetlevelname	Returns level name given level number	2-16
	HE5_PTgetreccnums	None	Retrieves number of records in one level corresponding to a group of records in a different level	2-17
	HE5_PTattrinfo	he5_ptattrinfo	Returns information about point attributes	2-03

Table 1-1. Summary of the Point Interface (2 of 2)

Category	Routine Name		Description	Pg. Nos.
	C	FORTTRAN		
	HE5_PTgrpatrinfo	he5_ptgrpatrinfo	Returns information about point group attributes	2-18
	HE5_PTlocatrinfo	he5_ptlocatrinfo	Returns information about point local attributes	2-26
	HE5_PTinqattr	he5_ptinqattr	Retrieves number and names of point attributes	2-19
	HE5_PTinqgrpattr	he5_ptinqgrpattr	Retrieves number and names of group attributes	2-20
	HE5_PTinqlocattr	he5_ptinqlocattr	Retrieves number and names of local attributes defined	2-21
	HE5_PTinqpoint	he5_ptinqpoint	Retrieves number and names of points in file	2-23
	HE5_PTinqdatatype	he5_ptinqdatatype	Returns data type information about specified level in point	2-35

1.4 Swath Data

The Swath (SW) interface consists of routines for storing, retrieving, and manipulating data in swath data sets. This interface is tailored to support time-ordered data such as satellite swaths (which consist of a time-ordered series of scanlines), or profilers (which consist of a time-ordered series of profiles). See the Users' Guide, Volume 1 that accompanies this document for more information.

1.4.1 The Swath Data Interface

All C routine names in the swath data interface have the prefix "HE5_SW" and the equivalent FORTRAN routine names are prefixed by "he5_sw." The Swath routines are classified into the following categories:

- **Access routines** initialize and terminate access to the Swath interface and Swath data sets (including opening and closing files).
- **Definition** routines allow the user to set key features of a Swath data set.
- **Basic I/O** routines read and write data and metadata to a Swath data set.
- **Inquiry** routines return information about data contained in a Swath data set.
- **Subset** routines allow reading of data from a specified geographic region.

1.4.2 List of Swath API Routines

The Swath function calls are listed below in Table 1-2 and are described in detail in Section 2 of this document. The listing in Section 2 is in alphabetical order.

Table 1-2. Summary of the Swath Interface (1 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Access	HE5_SWopen	he5_swopen	Opens or creates HDF file in order to create, read, or write a swath	2-103
	HE5_SWcreate	he5_swcreate	Creates a swath within the file	2-51
	HE5_SWattach	he5_swattach	Attaches to an existing swath within the file	2-47
	HE5_SWdetach	he5_swdetach	Detaches from swath interface	2-73
	HE5_SWclose	he5_swclose	Closes file	2-49
	HE5_SWdefdim	he5_swdefdim	Defines a new dimension within the swath	2-61
Definition	HE5_SWdefdimmap	he5_swdefmap	Defines the mapping between the geolocation and data dimensions	2-63
	HE5_SWdefidxmap	he5_swdefimap	Defines a non-regular mapping between the geolocation and data dimension	2-67
	HE5_SWdefgeofield	he5_swdefgfld	Defines a new geolocation field within the swath	2-65
	HE5_SWdefdatafield	he5_swdefdfld	Defines a new data field within the swath	2-59
	HE5_SWdefcomp	he5_swdefcomp	Defines a field compression scheme	2-57
	HE5_SWdefchunk	he5_swdefchunk	Define chunking parameters	2-54
	HE5_SWwritegeometa	he5_swwrgmeta	Writes field metadata for an existing swath geolocation field	2-128
	HE5_SWwritedatameta	he5_swwrdmeta	Writes field metadata for an existing swath data field	2-124
	HE5_SWdefcomchunk	he5_swdefcomch	Defines compression with automatic chunking	2-55
	HE5_SWsetalias	he5_swsetalias	Defines alias for data field	2-116
	HE5_SWdropalias	he5_swdrpalias	Removes alias from the list of field aliases	2-75
	HE5_SWfldrename	he5_swfldnm	Changes the field name	2-83
Basic I/O	HE5_SWaliasinfo	he5_swaliasinfo	Retrieves information about field aliases	2-46
	HE5_SWwrtfld	he5_swwrflld	Writes data to a swath field	2-125
	HE5_SWreadfld	he5_swrdfld	Reads data from a swath field.	2-108
	HE5_SWwriteattr	he5_swwrattr	Writes/updates attribute in a swath	2-122
	HE5_SWreadattr	he5_swrdattr	Reads attribute from a swath	2-106
	HE5_SWwritegrpattr	he5_swwrgattr	Writes/updates group attribute in a swath	2-130
	HE5_SWwritelocattr	he5_swwrlattr	Write/updates group attribute in a swath	2-132
	HE5_SWreadgrpattr	he5_swrdgattr	Reads attribute from a swath	2-110
	HE5_SWreadlocattr	he5_swrdlattr	Reads attribute from a swath	2-111
	HE5_SWsetfillvalue	he5_swsetfill	Sets fill value for the specified field	2-118
	HE5_SWgetfillvalue	he5_swgetfill	Retrieves fill value for the specified field	2-85
	HE5_SWinqdims	he5_swinqdims	Retrieves information about dimensions defined in swath	2-91
	HE5_SWinqmaps	he5_swinqmaps	Retrieves information about the geolocation relations defined	2-97
	HE5_SWinqidxmaps	he5_swinqimaps	Retrieves information about the indexed geolocation/data mappings defined	2-94
	HE5_SWinqgeofields	he5_swinqgflds	Retrieves information about the geolocation fields defined	2-92
	HE5_SWinqdatafields	he5_swinqdflds	Retrieves information about the data fields defined	2-90
	HE5_SWinqattrs	he5_swinqattrs	Retrieves number and names of attributes defined	2-89

Table 1-2. Summary of the Swath Interface (2 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Inquiry	HE5_SWinqrpattrs	he5_swinqgattr	Retrieve information about group attributes defined in swath	2-93
	HE5_SWinqlocattr	he5_swinqlattr	Retrieve information about local attributes defined in swath	2-95
	HE5_SWlocattrinfo	he5_swlocattrinfo	Returns information about a data field's local attribute(s)	2-99
	HE5_SWnentries	he5_swnentries	Returns number of entries and descriptive string buffer size for a specified entity	2-102
	HE5_SWdiminfo	he5_swdiminfo	Retrieve size of specified dimension	2-74
	HE5_SWmapinfo	he5_swmapinfo	Retrieve offset and increment of specified geolocation mapping	2-100
	HE5_SWidxmapinfo	he5_swidxmapinfo	Retrieve offset and increment of specified geolocation mapping	2-88
	HE5_SWattrinfo	he5_swattrinfo	Returns information about swath attributes	2-48
	HE5_SWgrpattrinfo	he5_swgattrinfo	Returns information about a swath group attribute	2-87
	HE5_SWfieldinfo	he5_swfldinfo	Retrieve information about a specific geolocation or data field	2-81
	HE5_SWcompinfo	he5_swcompinfo	Retrieve compression information about a field	2-50
	HE5_SWinqswath	he5_swinqswath	Retrieves number and names of swaths in file	2-98
	HE5_SWregionindex	he5_swregidx	Returns information about the swath region ID	2-112
	HE5_SWupdateidxmap	he5_swupimap	Update map index for a specified region	2-120
	HE5_SWgeomapinfo	he5_swgmapinfo	Retrieve type of dimension mapping for a dimension	2-86
Subset	HE5_SWdefboxregion	he5_swdefboxreg	Define region of interest by latitude/longitude	2-52
	HE5_SWregioninfo	he5_swreginfo	Returns information about defined region	2-114
	HE5_SWextractregion	he5_swextreg	Read a region of interest from a field	2-79
	HE5_SWdeftimeperiod	he5_swdeftmper	Define a time period of interest	2-68
	HE5_SWperiodinfo	he5_swperinfo	Returns information about a defined time period	2-104
	HE5_SWextractperiod	he5_swextper	Extract a defined time period	2-77
	HE5_SWdefvrtregion	he5_swdefvrtreg	Define a region of interest by vertical field	2-70
HE5_SWdupregion	he5_swdupreg	Duplicate a region or time period	2-76	
Profile	HE5_PRdefine	he5_prdefine	Defines profile data structure	2-134
	HE5_PRread	he5_prread	Reads profile data	2-138
	HE5_PRwrite	he5_prwrite	Writes profile data	2-141
	HE5_PRinquire	he5_prinquire	Retrieves information about profiles	2-137
	HE5_PRinfo	he5_prinfo	Return information about profile	2-135
	HE5_PRreclaimspace	Not available	Reclaims memory used by data buffer in HE5_PRread()call	2-140
External Files	HE5_SWmountexternal	Not available	Mount external data file	2-101
	HE5_SWreadexternal	Not available	Read external data set	2-107
	HE5_SWunmount	Not available	Dismount external data file	2-119
External	HE5_SWsetextdata	he5_swsetxdat	Set external data set	2-117
Data Sets	HE5_SWgetextdata	he5_swgetxdat	Get external data set	2-84

1.5 Grid Data

The Grid (GD) interface consists of routines for storing, retrieving, and manipulating data in Grid data sets. This interface is designed to support data that has been stored in a rectilinear array

based on a well defined and explicitly supported projection. See the Users' Guide, Volume 1 that accompanies this document for more details.

1.5.1 The Grid Data Interface

All C routine names in the Grid data interface have the prefix "HE5_GD" and the equivalent FORTRAN routine names are prefixed by "he5_gd." The GD routines are classified into the following categories:

- *Access routines* initialize and terminate access to the Grid interface and Grid data sets (including opening and closing files).
- *Definition* routines allow the user to set key features of a Grid data set.
- *Basic I/O* routines read and write data and metadata to a Grid data set.
- *Inquiry* routines return information about data contained in a Grid data set.
- *Subset* routines allow reading of data from a specified geographic region.

1.5.2 List of Grid API Routines

The Grid function calls are listed below in Table 1-3 and are described in detail in Section 2 of this document. The listing in Section 2 is in alphabetical order.

Table 1-3. Summary of the Grid Interface (1 of 3)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Access	HE5_GDopen	he5_gdopen	Creates a new file or opens an existing one	2-196
	HE5_GDcreate	he5_gdcreate	Creates a new grid in the file	2-150
	HE5_GDattach	he5_gdattach	Attaches to a grid	2-144
	HE5_GDdetach	he5_gddetach	Detaches from grid interface	2-171
	HE5_GDclose	he5_gdclose	Closes file	2-148
Definition	HE5_GDdeforigin	he5_gddeforigin	Defines origin of grid	2-160
	HE5_GDdefdim	he5_gddefdim	Defines dimensions for a grid	2-157
	HE5_GDdefproj	he5_gddefproj	Defines projection of grid	2-162
	HE5_GDdefpixreg	he5_gddefpixreg	Defines pixel registration within grid cell	2-161
	HE5_GDdeffield	he5_gddeffld	Defines data fields to be stored in a grid	2-158
	HE5_GDdefcomp	he5_gddefcomp	Defines a field compression scheme	2-154
	HE5_GDblkSOMoffset	None	This is a special function for SOM MISR data. Write block SOM offset values.	2-146
	HE5_GDdefcomtile	he5_gddefcomtle	Defines compression with automatic tiling	2-156

Table 1-3. Summary of the Grid Interface (2 of 3)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Basic I/O	HE5_GDwritefieldmeta	he5_gdwrmeta	Writes metadata for field already existing in file	2-214
	HE5_GDwritefield	he5_gdwrfld	Writes data to a grid field.	2-212
	HE5_GDreadfield	he5_gdrdfld	Reads data from a grid field	2-202
	HE5_GDwriteattr	he5_gdwrattr	Writes/updates attribute in a grid.	2-210
	HE5_GDwritelocattr	he5_gdwrlattr	Writes/updates group attribute in a grid	2-217
	HE5_GDwritegrpattr	he5_gdwrgattr	Writes/updates attribute in a grid	2-215
	HE5_GDreadattr	he5_gdrdatr	Reads attribute from a grid	2-201
	HE5_GDreadgrpattr	he5_gdrdgattr	Reads attribute from a grid	2-204
	HE5_GDreadlocattr	he5_gdrdlattr	Reads attribute from a grid	2-205
	HE5_GDsetfillvalue	he5_gdsetfill	sets fill value for the specified field	2-209
HE5_GDgetfillvalue	he5_gdgetfill	Retrieves fill value for the specified field	2-178	
Inquiry	HE5_GDinqdims	he5_gdinqdims	Retrieves information about dimensions defined in grid	2-186
	HE5_GDinqfields	he5_gdinqflds	Retrieves information about the data fields defined in grid	2-187
	HE5_GDinqattrs	he5_gdinqattrs	Retrieves number and names of attributes defined	2-185
	HE5_GDinqlocattrs	he5_gdinqlattrs	Retrieve information about local attributes defined for a field	2-190
	HE5_GDinqgrpattrs	he5_gdinqgattrs	Retrieve information about group attributes defined in grid	2-189
	HE5_GDnentries	he5_gdnentries	Returns number of entries and descriptive string buffer size for a specified entity	2-195
	HE5_GDgridinfo	he5_gdgridinfo	Returns dimensions of grid and X-Y coordinates of corners	2-183
	HE5_GDprojinfo	he5_gdprojinfo	Returns all GCTP projection information	2-200
	HE5_GDdiminfo	he5_gddiminfo	Retrieves size of specified dimension.	2-172
	HE5_GDcompinfo	he5_gdcompinfo	Retrieve compression information about a field	2-149
	HE5_GDfieldinfo	he5_gdfldinfo	Retrieves information about a specific geolocation or data field in the grid	2-175
	HE5_GDinqgrid	he5_gdinqgrid	Retrieves number and names of grids in file	2-188
	HE5_GDatrinfo	he5_gdatrinfo	Returns information about grid attributes	2-145
		HE5_GDgrpattrinfo	he5_gdgpattrinfo	Returns information about a swath group attribute
HE5_GDlocattrinfo		he5_gdlattrinfo	Returns information about a Data Field's local attribute(s)	2-194
HE5_GDorigininfo		he5_gdorginfo	Return information about grid origin	2-198
HE5_GDpixmapinfo		he5_gdpreginfo	Return pixel registration information for given grid	2-199
	HE5_GDdefboxregion	he5_gddefboxreg	Define region of interest by latitude/longitude	2-153
	HE5_GDregioninfo	he5_gdreginfo	Returns information about a defined region	2-206

Table 1-3. Summary of the Grid Interface (3 of 3)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
	HE5_GDextractregion	he5_gdextrreg	Read a region of interest from a field	2-174
Subset	HE5_GDdeftimeperiod	he5_gddefmeper	Define a time period of interest	2-167
	HE5_GDdefvrtregion	he5_gddefvrtreg	Define a region of interest by vertical field	2-169
	HE5_GDgetpixels	he5_gdgetpix	get row/columns for lon/lat pairs	2-179
	HE5_GDgetpixvalues	he5_gdgetpixval	get field values for specified pixels	2-181
	HE5_GDinterpolate	he5_gdinterpolate	Perform bilinear interpolation on a grid field	2-192
	HE5_GDdupregion	he5_gddupreg	Duplicate a region or time period	2-173
Tiling	HE5_GDdeftile	he5_gddeftle	Define a tiling scheme	2-164
External	HE5_GDsetextdata	he5_gdsetxdat	Set external data set	2-208
Data Sets	HE5_GDgetextdata	he5_gdgetxdat	Get external data set	2-171

1.6 GCTP Usage

The HDF-EOS Grid API uses the U.S. Geological Survey General Cartographic Transformation Package (GCTP) to define and subset grid structures. This section described codes used by the package.

1.6.1 GCTP Projection Codes

The following GCTP projection codes are used in the grid API described in Section 4 below:

HE5_GCTP_ALBERS		Albers Conical Equal-Area Projection
HE5_GCTP_MERCAT		Mercator Projection
HE5_GCTP_SPCS		State Plane Coordinate System
HE5_GCTP_GEO	(0)	Geographic
HE5_GCTP_UTM	(1)	Universal Transverse Mercator
HE5_GCTP_LAMCC	(4)	Lambert Conformal Conic
HE5_GCTP_PS	(6)	Polar Stereographic
HE5_GCTP_POLYC	(7)	Polyconic
HE5_GCTP_TM	(9)	Transverse Mercator
HE5_GCTP_LAMAZ	(11)	Lambert Azimuthal Equal Area
HE5_GCTP_HOM	(20)	Hotine Oblique Mercator
HE5_GCTP_SOM	(22)	Space Oblique Mercator
HE5_GCTP_GOOD	(24)	Interrupted Goode Homolosine
HE5_GCTP_ISINUS	(99/31)	Integerized Sinusoidal Projection*

* The Integerized Sinusoidal Projection is not part of the original GCTP package. It has been added by ECS. See *Level-3 SeaWiFS Data Products: Spatial and Temporal Binning Algorithms*. Additional references are provided in Section 2.

Note that other projections supported by GCTP will be adapted for HDF-EOS Version 5 as new user requirements are surfaced. For further details on the GCTP projection package, please refer to Section 6.3.4 and Appendix G of the SDP Toolkit Users Guide for the ECS Project, November 2000, (333-CD-600-001).

1.6.2 UTM Zone Codes

The Universal Transverse Mercator (UTM) Coordinate System uses zone codes instead of specific projection parameters. The table that follows lists UTM zone codes as used by GCTP Projection Transformation Package. C.M. is Central Meridian

Zone	C.M.	Range	Zone	C.M.	Range
01	177W	180W-174W	31	003E	000E-006E
02	171W	174W-168W	32	009E	006E-012E
03	165W	168W-162W	33	015E	012E-018E
04	159W	162W-156W	34	021E	018E-024E
05	153W	156W-150W	35	027E	024E-030E
06	147W	150W-144W	36	033E	030E-036E
07	141W	144W-138W	37	039E	036E-042E
08	135W	138W-132W	38	045E	042E-048E
09	129W	132W-126W	39	051E	048E-054E
10	123W	126W-120W	40	057E	054E-060E
11	117W	120W-114W	41	063E	060E-066E
12	111W	114W-108W	42	069E	066E-072E
13	105W	108W-102W	43	075E	072E-078E
14	099W	102W-096W	44	081E	078E-084E
15	093W	096W-090W	45	087E	084E-090E
16	087W	090W-084W	46	093E	090E-096E
17	081W	084W-078W	47	099E	096E-102E
18	075W	078W-072W	48	105E	102E-108E
19	069W	072W-066W	49	111E	108E-114E
20	063W	066W-060W	50	117E	114E-120E
21	057W	060W-054W	51	123E	120E-126E
22	051W	054W-048W	52	129E	126E-132E
23	045W	048W-042W	53	135E	132E-138E
24	039W	042W-036W	54	141E	138E-144E
25	033W	036W-030W	55	147E	144E-150E
26	027W	030W-024W	56	153E	150E-156E
27	021W	024W-018W	57	159E	156E-162E
28	015W	018W-012W	58	165E	162E-168E
29	009W	012W-006W	59	171E	168E-174E
30	003W	006W-000E	60	177E	174E-180W

1.6.3 GCTP Spheroid Codes

Clarke 1866 (default)	(0)
Clarke 1880	(1)
Bessel	(2)
International 1967	(3)
International 1909	(4)
WGS 72	(5)
Everest	(6)
WGS 66	(7)
GRS 1980	(8)
Airy	(9)
Modified Airy	(10)

Modified Everest	(11)
WGS 84	(12)
Southeast Asia	(13)
Australian National	(14)
Krassovsky	(15)
Hough	(16)
Mercury 1960	(17)
Modified Mercury 1968	(18)
Sphere of Radius 6370997m	(19)

1.6.4 GCTP Projection Parameters

Table 1-4. Projection Transformation Package Projection Parameters (1 of 2)

Code & Projection Id	Array Element							
	1	2	3	4	5	6	7	8
0 Geographic								
1 U T M	Lon/Z	Lat/Z						
4 Lambert Conformal C	SMajor	SMinor	STDPR1	STDPR2	CentMer	OriginLat	FE	FN
6 Polar Stereographic	SMajor	SMinor			LongPol	TrueScale	FE	FN
7 Polyconic	SMajor	SMinor			CentMer	OriginLat	FE	FN
9 Transverse Mercator	SMajor	SMinor	Factor		CentMer	OriginLat	FE	FN
11 Lambert Azimuthal	Sphere				CentLon	CenterLat	FE	FN
20 Hotin Oblique Merc A	SMajor	SMinor	Factor			OriginLat	FE	FN
20 Hotin Oblique Merc B	SMajor	SMinor	Factor	AziAng	AzmthPt	OriginLat	FE	FN
22 Space Oblique Merc A	SMajor	SMinor		IncAng	AscLong		FE	FN
22 Space Oblique Merc B	SMajor	SMinor	Satnum	Path			FE	FN
24 Interrupted Goode	Sphere							
99 Integerized Sinusoidal	Sphere				CentMer		FE	FN

Table 1-4. Projection Transformation Package Projection Parameters (2 of 2)

Code & Projection Id	Array Element				
	9	10	11	12	13
0 Geographic					
1 U T M					
4 Lambert Conformal C					
6 Polar Stereographic					
7 Polyconic					
9 Transverse Mercator					
11 Lambert Azimuthal					
20 Hotin Oblique Merc A	Long1	Lat1	Long2	Lat2	Zero
20 Hotin Oblique Merc B					One
22 Space Oblique Merc A	PSRev	Srat	PFlag	HDF-EOS Variable	Zero
22 Space Oblique Merc B				HDF-EOS Variable	One
24 Interrupted Goode					
99 Integerized Sinusoidal	Nzone		RFlag		

Where,

Lon/Z Longitude of any point in the UTM zone or zero. If zero, a zone code must be specified.

Lat/Z Latitude of any point in the UTM zone or zero. If zero, a zone code must be specified.

Smajor Semi-major axis of ellipsoid. If zero, Clarke 1866 in meters is assumed.

Sminor Eccentricity squared of the ellipsoid if less than zero, if zero, a spherical form is assumed, or if greater than zero, the semi-minor axis of ellipsoid.

Sphere Radius of reference sphere. If zero, 6370997 meters is used.

STDPR1 Latitude of the first standard parallel

STDP2	Latitude of the second standard parallel
CentMer	Longitude of the central meridian
OriginLat	Latitude of the projection origin
FE	False easting in the same units as the semi-major axis
FN	False northing in the same units as the semi-major axis
TrueScale	Latitude of true scale
LongPol	Longitude down below pole of map
Factor	Scale factor at central meridian (Transverse Mercator) or center of projection (Hotine Oblique Mercator)
CentLon	Longitude of center of projection
CenterLat	Latitude of center of projection
Long1	Longitude of first point on center line (Hotine Oblique Mercator, format A)
Long2	Longitude of second point on center line (Hotine Oblique Mercator, frmt A)
Lat1	Latitude of first point on center line (Hotine Oblique Mercator, format A)
Lat2	Latitude of second point on center line (Hotine Oblique Mercator, format A)
AziAng	Azimuth angle east of north of center line (Hotine Oblique Mercator, frmt B)
AzmthPt	Longitude of point on central meridian where azimuth occurs (Hotine Oblique Mercator, format B)
IncAng	Inclination of orbit at ascending node, counter-clockwise from equator (SOM, format A)
AscLong	Longitude of ascending orbit at equator (SOM, format A)
PSRev	Period of satellite revolution in minutes (SOM, format A)
SRat	Satellite ratio to specify the start and end point of x,y values on earth surface (SOM, format A -- for Landsat use 0.5201613)
PFlag	End of path flag for Landsat: 0 = start of path, 1 = end of path (SOM, frmt A)
Satnum	Landsat Satellite Number (SOM, format B)
Path	Landsat Path Number (Use WRS-1 for Landsat 1, 2 and 3 and WRS-2 for Landsat 4 and 5.) (SOM, format B)

Nzone	Number of equally spaced latitudinal zones (rows); must be two or larger and even
Rflag	Right justify columns flag is used to indicate what to do in zones with an odd number of columns. If it has a value of 0 or 1, it indicates the extra column is on the right (zero) or left (one) of the projection Y-axis. If the flag is set to 2 (two), the number of columns are calculated so there are always an even number of columns in each zone.

Notes:

- HDF-EOS variable is used by the library function HE5_GDbklsomoffset.
- Array elements 14 and 15 are set to zero.
- All array elements with blank fields are set to zero.

All angles (latitudes, longitudes, azimuths, etc.) are entered in packed degrees/ minutes/ seconds (DDMMSS.SS) format.

The following notes apply to the Space Oblique Mercator A projection:

- A portion of Landsat rows 1 and 2 may also be seen as parts of rows 246 or 247. To place these locations at rows 246 or 247, set the end of path flag (parameter 11) to 1--end of path. This flag defaults to zero.
- When Landsat-1,2,3 orbits are being used, use the following values for the specified parameters:
 - Parameter 4 099005031.2
 - Parameter 5 128.87 degrees - (360/251 * path number) in packed DMS format
 - Parameter 9 103.2669323
 - Parameter 10 0.5201613
- When Landsat-4,5 orbits are being used, use the following values for the specified parameters:
 - Parameter 4 098012000.0
 - Parameter 5 129.30 degrees - (360/233 * path number) in packed DMS format
 - Parameter 9 98.884119
 - Parameter 10 0.5201613

This page intentionally left blank.

2. Function Reference

2.1 Format

This section contains a function-by-function reference for each interface in the HDF-EOS library. Each function has a separate page describing it (in some cases there are multiple pages). Each page contains the following information (in order):

- Function name as used in C
- Function declaration in ANSI C format
- Description of each argument
- Purpose of routine
- Description of returned value
- Description of the operation of the routine
- A short example of how to use the routine in C
- The FORTRAN declaration of the function and arguments
- An equivalent FORTRAN example

2.1.1 Point Interface Functions

This section contains an alphabetical listing of all the functions in the Point interface. The functions are alphabetized based on their C-language names.

Attach to an Existing Point Structure

HE5_PTattach

hid_t HE5_PTattach(hid_t *fid*, const char **pointname*)

fid IN: Point file ID returned by HE5_PTopen

pointname IN: Name of point to be attached

Purpose Attaches to an existing point within the file.

Return value Returns the point handle (pointID) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point file ID or point name.

Description This routine attaches to the point using the *pointname* parameter as the identifier.

Example In this example, we attach to the previously created point, "ExamplePoint", within the HDF-EOS file, *Point.he5*, referred to by the handle, *fid*:

```
pointID = HE5_PTattach(fid, "ExamplePoint");
```

The point can then be referenced by subsequent routines using the handle, *pointID*.

FORTRAN integer function he5_ptattach(*fid*,*pointname*)

integer *fid*

character*(*) *pointname*

The equivalent *FORTRAN* code for the example above is:

```
pointid = he5_ptattach(fid, "ExamplePoint")
```

Return Information About a Point Attribute

HE5_PTattrinfo

herr_t HE5_PTattrinfo(hid_t *pointID*, const char **attrname*, H5T_class_t **numbertype*, hsize_t **count*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

numbertype OUT: Data type class ID of attribute

count OUT: Number of total bytes in attribute

Purpose Returns information about a point attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (*count*) of a point attribute.

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_PTattrinfo(pointID, "ScalarFloat", &nt, &count);
```

The *nt* variable will have the value 1 and *count* will have the value 4.

FORTRAN integer function he5_ptattrinfo(*pointid*, *attrname*, *ntype*, *count*)

integer *pointid*

character *(*) *attrname*

integer *ntype*

integer*4 *count*

The equivalent *FORTRAN* code for the example above is:

```
pointid = he5_ptattrinfo(pointid, "ScalarFloat", ntype, count)
```

Return Linkage Field to Previous Level

HE5_PTbcklinkinfo

herr_t HE5_PTbcklinkinfo(hid_t *pointID*, int *level*, char **linkfield*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Point level (0-based)

linkfield OUT: Link field

Purpose Returns the linkfield to the previous level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns the linkfield to the previous level.

Example In this example, we return the linkfield connecting the *Observations* level to the previous *Desc-Loc* level. (This levels are defined in the *HE5_PTdeflevel* routine.)

```
status = HE5_PTbcklinkinfo(pointID2, 1, linkfield);
```

The *linkfield* will contain the string: *ID*.

FORTRAN integer function he5_ptbcklinkinfo(*pointid,level,linkfield*)

integer *pointid,status*

character *(*) *linkfield*

integer *level*

The equivalent *FORTRAN* code for the example above is:

```
level = 1
```

```
status = he5_ptbcklinkinfo(pointid, level, linkfield)
```

Close an HDF-EOS File

HE5_PTclose

herr_t HE5_PTclose(hid_t *fid*)

fid IN: Point file ID returned by HE5_PTopen

Purpose Closes file.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine closes the HDF-EOS Point file.

Example

```
status = HE5_PTclose(fid);
```

FORTRAN integer function he5_ptclose(*fid*)

integer *fid*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptclose(fid)
```

Create a New Point Structure

HE5_PTcreate

hid_t HE5_PTcreate(hid_t *fid*, const char **pointname*)

fid IN: Point file ID returned by HE5_PTopen

pointname IN: Name of point to be created

Purpose Creates a point within the file.

Return value Returns the point handle (*pointID*) if successful or FAIL (-1) otherwise.

Description The point is created as a Compound dataset within the HDF-EOS file with the name *pointname* .

Example In this example, we create a new point structure, *ExamplePoint*, in the previously created file, *Point.he5*.

```
pointID = HE5_PTcreate(fid, "ExamplePoint");
```

The point structure is then referenced by subsequent routines using the handle, *pointID*.

FORTTRAN integer function he5_ptcreate(*fid*,*pointname*)

integer *pointid*, *fid*

character *(*) *pointame*

The equivalent *FORTTRAN* code for the example above is:

```
pointid = he5_ptcreate(fid, "ExamplePoint")
```

Define a New Level Within a Point

HE5_PTdeflevel

herr_t HE5_PTdeflevel(hid_t *pointID*, const char **levelname*, HE5_CmpDTSinfo **levelinfo*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach
levelname IN: Name of level to be defined
levelinfo IN: C-data structure containing all necessary information about level to be defined

Note: Merging is not supported in this release of the library. There are three illegal characters for field names: “/”, “;”, “,”

Purpose Defines a new level within the point.
Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description This routine defines a level within the point. A simple point consists of a single level. A point where there is common data for a number of records can be more efficiently stored with multiple levels. The order in which the levels are defined determines the (0-based) level index.
Example Simple Point

In this example, we define a simple single level point, with levelname, *Sensor*. The levelname should not contain any slashes (“/”). It consists of six fields, *ID*, *Time*, *Longitude*, *Latitude*, *Temperature*, and *Mode* defined in the field list. The *fieldtype* and *fieldorder* parameters are arrays consisting of the HDF number type codes and field orders, respectively. The *Temperature* is an array field of dimension 4 and the *Mode* field a character string of size 4. All other fields are scalars. Note that the order for numerical scalar variables can be either 0 or 1.

```
typedef struct {  
    int    id;  
    int    time;  
    float  lon;  
    float  lat;  
    float  temp[4];
```

```

        char    mode[4];
    } InputData1;
HE5_CmpDTSinfo  dtsinfo;
dtsinfo.nfields = 6;
dtsinfo.rank[0] = 1;
dtsinfo.rank[1] = 1;
dtsinfo.rank[2] = 1;
dtsinfo.rank[3] = 1;
dtsinfo.rank[4] = 1;
dtsinfo.rank[5] = 1;
for (i = 0; i < 6; i++)
    dtsinfo.fieldname[i] = (char
*)malloc(64,sizeof(char));

strcpy(dtsinfo.fieldname[0], "ID");
strcpy(dtsinfo.fieldname[1], "Time");
strcpy(dtsinfo.fieldname[2], "Longitude");
strcpy(dtsinfo.fieldname[3], "Latitude");
strcpy(dtsinfo.fieldname[4], "Temperature");
strcpy(dtsinfo.fieldname[5], "Mode");

dtsinfo.offset[0] = HOFFSET(InputData1, id);
dtsinfo.offset[1] = HOFFSET(InputData1, time);
dtsinfo.offset[2] = HOFFSET(InputData1, lon);
dtsinfo.offset[3] = HOFFSET(InputData1, lat);
dtsinfo.offset[4] = HOFFSET(InputData1, temp);
dtsinfo.offset[5] = HOFFSET(InputData1, mode);

dtsinfo.datatype[0] = H5T_NATIVE_INT;
dtsinfo.datatype[1] = H5T_NATIVE_INT;

```

```

dtsinfo.datatype[2] = H5T_NATIVE_FLOAT;
dtsinfo.datatype[3] = H5T_NATIVE_FLOAT;
dtsinfo.datatype[4] = H5T_NATIVE_FLOAT;
dtsinfo.datatype[5] = H5T_NATIVE_CHAR;

dtsinfo.dims[0][0] = 1;
dtsinfo.dims[1][0] = 1;
dtsinfo.dims[2][0] = 1;
dtsinfo.dims[3][0] = 1;
dtsinfo.dims[4][0] = 4;
dtsinfo.dims[5][0] = 4;

dtsinfo.datasize = sizeof(InputData1);
status = HE5_PTdeflevel(pointID1, "Sensor", &dtsinfo);
for (i = 0; i < 6; i++)
    free(dtsinfo.fieldname[i]);

```

Multi-Level Point

In this example, we define a two-level point that describes data from a network of fixed buoys. The first level contains information about each buoy and includes the name (label) of the buoy, its (fixed) longitude and latitude, its deployment date, and an ID that is used to link it to the following level. (The link field is defined in the *HE5_PTdeflinkage* routine described later.) The entries within this ID field must be unique. The second level contains the actual measurements from the buoys (rainfall and temperature values) plus the observation time and the ID which relates a given measurement to a particular buoy entry in the previous level. There can be many records in this level with the same ID since there can be multiple measurements from a single buoy. It is advantageous, although not mandatory, to store all records for a particular buoy (ID) contiguously.

Level 0

```

HE5_CmpDTSinfo  lev0_info;
typedef struct {
    char    label[8];

```

```

        double   lon;

        double   lat;

        float    deploydate;

        char     id;
    } Lev0_Data;

    lev0_info.nfields = 5;
    lev0_info.rank[0] = 1;
    lev0_info.rank[1] = 1;
    lev0_info.rank[2] = 1;
    lev0_info.rank[3] = 1;
    lev0_info.rank[4] = 1;
    for (i = 0; i < 5; i++)
        lev0_info.fieldname[i] = (char
*)calloc(64,sizeof(char));

    strcpy(lev0_info.fieldname[0], "Label");
    strcpy(lev0_info.fieldname[1], "Longitude");
    strcpy(lev0_info.fieldname[2], "Latitude");
    strcpy(lev0_info.fieldname[3], "DeployDate");
    strcpy(lev0_info.fieldname[4], "ID");

    lev0_info.offset[0] = HOFFSET(Lev0_Data, label);
    lev0_info.offset[1] = HOFFSET(Lev0_Data, lon);
    lev0_info.offset[2] = HOFFSET(Lev0_Data, lat);
    lev0_info.offset[3] = HOFFSET(Lev0_Data, deploydate);
    lev0_info.offset[4] = HOFFSET(Lev0_Data, id);

    lev0_info.datatype[0] = H5T_NATIVE_CHAR;
    lev0_info.datatype[1] = H5T_NATIVE_DOUBLE;
    lev0_info.datatype[2] = H5T_NATIVE_DOUBLE;

```

```

lev0_info.datatype[3] = H5T_NATIVE_FLOAT;
lev0_info.datatype[4] = H5T_NATIVE_CHAR;

lev0_info.dims[0][0] = 8;
lev0_info.dims[1][0] = 1;
lev0_info.dims[2][0] = 1;
lev0_info.dims[3][0] = 1;
lev0_info.dims[4][0] = 1;

lev0_info.datasize = sizeof(Lev0_Data);

status = HE5_PTdeflevel(pointID2, "Desc-Loc", &lev0_info);
for (i = 0; i < 5; i++)
    free (lev0_info.fieldname[i]);

```

Level 1

```

HE5_CmpDTSinfo  lev1_info;
typedef struct {
    double  time;
    float   rain;
    float   temp;
    char    id;
} Lev1_Data;
lev1_info.nfields = 4;
lev1_info.rank[0] = 1;
lev1_info.rank[1] = 1;
lev1_info.rank[2] = 1;
lev1_info.rank[3] = 1;
for (i = 0; i < 4; i++)
    lev1_info.fieldname = (char *)calloc(64,sizeof(char));

```

```

strcpy(levl_info.fieldname[0], "Time");
strcpy(levl_info.fieldname[1], "Rainfall");
strcpy(levl_info.fieldname[2], "Temperature");
strcpy((levl_info.fieldname[3], "ID");

levl_info.offset[0] = HOFFSET(Levl_Data, time);
levl_info.offset[1] = HOFFSET(Levl_Data, rain);
levl_info.offset[2] = HOFFSET(Levl_Data, temp);
levl_info.offset[3] = HOFFSET(Levl_Data, id);

levl_info.datatype[0] = H5T_NATIVE_DOUBLE;
levl_info.datatype[1] = H5T_NATIVE_FLOAT;
levl_info.datatype[2] = H5T_NATIVE_FLOAT;
levl_info.datatype[3] = H5T_NATIVE_CHAR;

levl_info.dims[0][0] = 1;
levl_info.dims[1][0] = 1;
levl_info.dims[2][0] = 1;
levl_info.dims[3][0] = 1;

levl_info.datasize = sizeof(Levl_Data);

status = HE5_PTdeflevel(pointID2, "Observations",
&levl_info);

for (i = 0; i < 4; i++)
    free(levl_info.fieldname[i]);

```

FORTTRAN See Example 2 from Section 7.1.1.2 of Volume 1 (Overview and Examples)

Define Linkage Field Between Two Levels

HE5_PTdeflinkage

herr_t HE5_PTdeflinkage(hid_t *pointID*, char **parent*, char **child*, char **linkfield*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

parent IN: Name of parent level

child IN: Name of child level

linkfield IN: Name of (common) link field

Purpose Defines a link field between two (adjacent) levels.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine defines the link field between two levels. This field must be defined in both levels.

Note The defining of a linkage is necessary if more than one level is defined.

Example In this example we define the *ID* field as the link between the two levels defined previously in the *HE5_PTdeflevel* routine.

```
status = HE5_PTdeflinkage(pointID2, "Desc-Loc",  
"Observations", "ID");
```

FORTTRAN integer function
he5_ptdeflinkage(*pointid*,*levelname1*,*levelname2*,*linkname*)

integer *pointid*,*status*

character *(*) *linkname*,*levelname1*,*levelname2*

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_ptdeflinkage(pointid, "Desc-Loc",  
"Observations", "ID")
```

Detach from Point Structure

HE5_PTdetach

herr_t HE5_PTdetach(hid_t *pointID*)

- pointID* IN: Point ID returned by HE5_PTcreate or HE5_PTattach
- Purpose Detaches from point data set.
- Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
- Description This routine should be run before exiting from the point file for every point opened by *HE5_PTcreate* or *HE5_PTattach*.
- Example In this example, we detach the point structure, *ExamplePoint*:

```
status = HE5_PTdetach(pointID);
```

FORTRAN integer function he5_ptdetach(*pointid*)

integer *pointid, status*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptdetach(pointid)
```

Return Linkage Field to Following Level

HE5_PTfwdlinkinfo

herr_t HE5_PTfwdlinkinfo(hid_t *pointID*, int *level*, char **linkfield*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Point level (0-based)

linkfield OUT: Link field

Purpose Returns the link field to the following level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns the link field to the following level.

Example In this example, we return the link field connecting the *Desc-Loc* level to the following *Observations* level. (These levels are defined in the *HE5_PTdeflevel* routine.)

```
status = HE5_PTfwdlinkinfo(pointID2, 1, linkfield);
```

The *linkfield* will contain the string: *ID*.

FORTRAN integer function he5_ptfwdlinkinfo(*pointid,level,linkfield*)

integer *pointid,status*

character *(*) *linkfield*

integer *level*

The equivalent *FORTRAN* code for the example above is:

```
level = 1
```

```
status = he5_ptfwdlinkinfo(pointid, level, linkfield)
```

Return Level Name

HE5_PTgetlevelname

herr_t HE5_PTgetlevelname(hid_t *pointID*, int *level*, char **levelname*, long **strbufsize*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Point level (0-based)

levelname OUT: Level name

strbufsize OUT: String length of level name

Purpose Returns the name of a level given the level number.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns the name of a level given the level number (0-based). If the user passes NULL for the level name, the routine will return just the string length of the level name (not counting the null terminator).

Example In this example, we return the level name of the 0th level of the second point defined in the *HE5_PTdeflevel* section:

```
status = HE5_PTgetlevelname(pointID2, 0, levelname,
&strbufsize);
```

The *levelname* will contain the string: *Desc-Loc* and the *strbufsize* variable will be set to 8.

FORTTRAN integer function he5_ptgetlevelname(*pointid*,*level*,*levelname*,*strbufsz*)

integer *pointid*,*status*,*level*

character *(*) *levelname*

integer*4 *strbufsz*

The equivalent *FORTTRAN* code for the example above is:

```
level = 0
```

```
status = he5_ptgetlevelname(pointid, level, levelname,
strbufsz)
```

Return Record Numbers Related to Level

HE5_PTgetrecnums

herr_t HE5_PTgetrecnums(hid_t *pointID*, int *inlevel*, int *outlevel*, hsize_t *inNrec*,
hssize_t *inRecs*[], hsize_t **outNrec*, hssize_t *outRecs*[])

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

inlevel IN: Level number of input records(0-based)

outlevel IN: Level number of output records(0-based)

inNrec IN: Number of records in the *inRecs* array

inRecs IN: Array containing the input record numbers.

outNrec OUT: Number of records in the *outRecs* array

outRecs OUT Array containing the output record numbers.

Purpose Returns the record numbers in one level corresponding to a group of records in a different level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description The records in one level are related to those in another through the link field. These in turn are related to the next. In this way each record in any level is related to others in all the levels of the point structure. The purpose of *HE5_PTgetrecnums* is to return the record numbers in one level that are connected to a given set of records in a different level. Note that the two levels need not be adjacent.

Example In this example, we get the record number in the second level that are related to the first record in the first level.

```
nrec = 1;  
recs[0] = 0;  
inLevel = 0;  
outLevel = 1;  
  
status = HE5_PTgetrecnums(pointID2, inLevel, outLevel, nrec,  
recs, &outNrec, outRecs);
```

FORTRAN Not available with this release.

Return Information About Group Attribute

HE5_PTgrpattrinfo

herr_t HE5_PTgrpattrinfo(hid_t *pointID*, const char **attrname*, H5T_class_t **numbertype*, hsize_t **count*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

numbertype OUT: Data type class ID of attribute

count OUT: Number of total bytes in attribute

Purpose Returns information about attribute associated with the point “Data” group

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (*count*) of an attribute associated with the point “Data” group.

Example In this example, we return information about the *GroupFloat* attribute.

```
status = HE5_PTgrpattrinfo(pointID,  
"GroupFloat", &nt, &count);
```

The *nt* variable will have the value 1 and *count* will have the value 4.

FORTRAN integer function he5_ptgrpattrinfo(*pointid*,*attrname*,*ntype*,*count*)

integer *pointid*,*status*

integer*4 *count*

integer *ntype*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptgrpattrinfo(pointid, "GroupFloat", ntype,  
count)
```

Retrieve Information About Point Attributes

HE5_PTinqattrs

long HE5_PTinqattrs(hid_t *pointID*, char **attrlist*, long **strbufsize*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrlist OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about attributes defined in point.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the attributes defined in a point structure. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_PTinqattrs(pointID, NULL, strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_PTinqattrs(pointID, attrlist, strbufsize);
```

The variable, *attrlist*, will be set to:

```
"attrOne,attr_2".
```

FORTRAN integer*4 function he5_ptinqattrs(*pointid*,*attrlist*,*strbufsz*)

integer *pointid*

character *(*) *attrlist*

integer*4 *nattr*, *strbufsz*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_ptinqattrs(pointid, attrlist, strbufsz)
```

Retrieve Information About Group Attributes

HE5_PTinqgrpattrs

long HE5_PTinqgrpattrs(hid_t *pointID*, char **attrlist*, long **strbufsize*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrlist OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about attributes defined in point “Data” group.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the attributes defined in the “Data” group of point structure. We assume that there are two attributes stored, *GrpAttrOne* and *GrpAttr_2*:

```
nattr = HE5_PTinqgrpattrs(pointID, NULL, strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 20.

```
nattr = HE5_PTinqgrpattrs(pointID, attrlist, strbufsize);
```

The variable, *attrlist*, will be set to:

```
"GrpAttrOne,GrpAttr_2".
```

FORTRAN integer*4 function he5_ptinqgrpattrs(*pointid*,*attrlist*,*strbufsz*)

integer *pointid*

character *(*) *attrlist*

integer*4 *nattr*,*strbufsz*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_ptinqgrpattrs(pointid, attrlist, strbufsz)
```

Retrieve Information About Level Attributes

HE5_PTinqlocattr

long HE5_PTinqlocattr(hid_t *pointID*, const char **levelname*, char **attrlist*, long **strbufsize*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

levelname IN: Level name

attrlist OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about attributes defined for a specified level in a point.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the local attributes defined for the *Observations* level in a point structure. We assume that there are two attributes stored, *LocAttrOne* and *LocAttrTwo*:

```
nattr = HE5_PTinqlocattr(pointID, "Observations", NULL,
strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 21.

```
nattr = HE5_PTinqlocattr(pointID, levelname, attrlist,
strbufsize);
```

The variable, *attrlist*, will be set to:

"LocAttrOne,LocAttrTwo".

FORTRAN integer*4 function
he5_ptinqlocattr(*pointid*,*levelname*,*attrlist*,*strbufsz*)
integer *pointid*

```
character *(*) levelname, attrlist
```

```
integer*4      nattr, strbufsz
```

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_ptinqlocattrrs(pointid, levelname, attrlist,  
strbufsz)
```

Retrieve Point Structures Defined in HDF-EOS File

HE5_PTinqpoint

int HE5_PTinqpoint(const char * *filename*, char **pointlist*, long **strbufsize*)

filename IN: HDF-EOS filename

pointlist OUT: Point list (entries separated by commas)

strbufsize OUT: String length of point list

Purpose Retrieves number and names of points defined in HDF-EOS file.

Return value Number of points found if successful or FAIL (-1) otherwise.

Description The point list is returned as a string with each point name separated by commas. If *pointlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. If *strbufsize* is also set to NULL, the routine returns just the number of points. Note that *strbufsize* does not count the null string terminator.

Example In this example, we retrieve information about the points defined in an HDF-EOS file, *Point.he5*. We assume that there are two points stored, *PointOne* and *Point_2*:

```
npoint = HE5_PTinqpoint("Point.he5", NULL, strbufsize);
```

The parameter, *npoint*, will have the value 2 and *strbufsize* will have value 16.

```
npoint = HE5_PTinqpoint("Point.he5", pointlist, strbufsize);
```

The variable, *pointlist*, will be set to:

"PointOne,Point_2".

FORTRAN integer function he5_ptinqpoint(*filename,pointlist,strbufsz*)

integer *npoint*

character *(*) *pointlist*

integer*4 *strbufsz*

The equivalent *FORTRAN* code for the example above is:

```
npoint = he5_ptinqpoint("Point.he5", pointlist, strbufsz)
```

Return Index Number of a Named Level

HE5_PTlevelindx

int HE5_PTlevelindx(hid_t *pointID*, const char **levelname*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

levelname IN: Level Name

Purpose Returns the level index (0-based) for a given (named) level.

Return value Returns the level index if successful or FAIL (-1) otherwise.

Description This routine returns the level index for a give level specified by name.

Example In this example, we return the level index of the *Observations* level in the multilevel point structure defined in *HE5_PTdeflevel*.

```
levindx = HE5_PTlevelindx(pointID2, "Observations");
```

The *levindx* variable will have the value 1.

FORTTRAN integer function he5_ptlevelindx(*pointid*,*levelname*)

integer *pointid*,*levindx*

character *(*) *levelname*

The equivalent *FORTTRAN* code for the example above is:

```
levindx = he5_ptlevelindx(pointid, "Observations")
```

Return Information on Fields in a Given Level

HE5_PTlevelinfo

herr_t HE5_PTlevelinfo(hid_t *pointID*, int *level*, HE5_CmpDTSinfo **info*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Point level (0-based)

info OUT: C-data structure containing the level information

Purpose Returns information on fields in a given level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or level number.

Description This routine returns information about the fields in a given level.

Example In this example we return information about the *Desc-Loc* (1st) level defined previously.

```
HE5_CmpDTSinfo      lev0_info;  
  
status = HE5_PTlevelinfo(pointID2, 0, &lev0_info);
```

The *lev0_info.nfields* data member will be set to 5. The *lev0_info.fieldname* array will be "Time,Longitude,Latitude,Channel,Value".

FORTTRAN See Example 4 from Section 7.1.1.2 of Volume 1 (Overview of Examples).

Return Information About Level Attribute

HE5_PTlocattrinfo

herr_t HE5_PTlocattrinfo(hid_t *pointID*, const char **levelname*, const char **attrname*, H5T_class_t **numbertype*, hsize_t **count*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_Ptattach

levelname IN: Level name

attrname IN: Attribute name

numbertype OUT: Data type class ID of attribute

count OUT: Number of total bytes in attribute

Purpose Returns information about point level attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of an attribute associated with a specified level.

Example In this example, we return information about the *LocalFloat* attribute associated with the level *Observations*.

```
status = HE5_Ptattrinfo(pointID,  
"Observations", "LocalFloat", &nt, &count);
```

The *nt* variable will have the value 1 and *count* will have the value 4.

FORTRAN integer function he5_ptlocattrinfo(*pointid*, *levelname*, *attrname*, *ntype*, *count*)

integer *pointid*, *status*, *ntype*

character *(*) *levelname*, *attrname*

integer*4 *count*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptlocattrinfo(pointid, "Observations",  
"LocalFloat", ntype, count)
```

Return Number of Fields Defined in a Level

HE5_PTnfields

int HE5_PTnfields(hid_t *pointID*, int *level*, char **fieldlist*, long **strbufsize*)

<i>pointID</i>	IN: Point ID returned by HE5_PTcreate or HE5_PTattach
<i>level</i>	IN: Level number (0-based)
<i>fieldlist</i>	OUT: Field list (entries separated by commas)
<i>strbufsize</i>	OUT: Size in bytes of fieldlist for level
Purpose	Returns number of fields in a level and the size of the fieldlist.
Return value	Returns number of fields if successful or FAIL (-1) otherwise.
Description	This routine returns the number of fields in a level and the size of the comma-separated fieldlist. This value does NOT count the null character at the end of the string.
Example	In this example we retrieve the number of levels in the 2nd point defined previously: <pre>nflds = HE5_PTnfields(pointID2, 0, NULL, &strbufsize); nflds = HE5_PTnfields(pointID2, 0, fieldlist, &strbufsize);</pre> The <i>nflds</i> variable will be 5 and the <i>strbufsize</i> variable equal to 38.

FORTRAN integer function he5_ptnfields(*pointid2*,*level*,*fieldlist*,*strbufsz*)

integer *pointid2*,*level*,*nflds*

character *(*) *fieldlist*

integer*4 *strbufsz*

The equivalent *FORTRAN* code for the example above is:

```
level = 0
```

```
nflds = he5_ptnfields(pointid2, level, fieldlist, strbufsz)
```

Return Number of Levels in a Point Structure

HE5_PTnlevels

int HE5_PTnlevels(hid_t *pointID*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

Purpose Returns number of levels in a point.

Return value Returns number of levels if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID.

Description This routine returns the number of levels in a point.

Example In this example we retrieve the number of levels in the 2nd point defined previously:

```
nlevels = HE5_PTnlevels(pointID2);
```

The *nlevels* variable will be 2.

FORTRAN integer function he5_ptnlevels(*pointid*)

integer *pointid,nlevels*

The equivalent *FORTRAN* code for the example above is:

```
nlevels = he5_ptnlevels(pointid)
```

Return Number of Records in a Given Level

HE5_PTnrecs

hsize_t HE5_PTnrecs(hid_t *pointID*, int *level*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Level number (0-based)

Purpose Returns number of records in a given level.

Return value Returns number of records in a given level if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or level number.

Description This routine returns the number of records in a given level.

Example In this example we retrieve the number of records in the first level of the 2nd point defined previously:

```
nrecs = HE5_PTnrecs(pointID2, 0);
```

FORTTRAN integer function he5_ptnrecs(*pointid,level*)

integer *pointid2,level*

The equivalent *FORTTRAN* code for the example above is:

```
level = 0
```

```
status = he5_ptnrecs(pointid2, level)
```

Open HDF-EOS File

HE5_PTopen

hid_t HE5_PTopen(const char *filename, uintn access)

<i>filename</i>	IN: Complete path and filename for the file to be opened
<i>access</i>	IN: H5F_ACC_RDONLY, H5F_ACC_RDWR or H5F_ACC_TRUNC
Purpose	Opens or creates HDF-EOS file in order to create, read, or write a point.
Return value	Returns the point file ID (fid) if successful or FAIL (-1) otherwise.
Description	This routine creates a new file or opens an existing one, depending on the access parameter.
	Access codes:
	H5F_ACC_RDONLY Open for read only. If file does not exist, error
	H5F_ACC_RDWR Open for read/write. If file does not exist, error
	H5F_ACC_TRUNC If file exists, delete it, then open a new file for read/write
Example	In this example, we create a new point file named, <i>Point.he5</i> . It returns the file handle, <i>fid</i> .

```
fid = HE5_PTopen("Point.he5", H5F_ACC_TRUNC);
```

FORTRAN integer function he5_ptopen(*filename,flag*)

integer *fid*

character *(*) *filename*

integer *HE5_HDFE_TRUNC*

parameter (*HE5_HDFE_TRUNC=2*)

The equivalent *FORTRAN* code for the example above is:

```
fid = he5_ptopen("Point.he5", HE5_HDFE_TRUNC)
```

Read Point Attribute

HE5_PTreadattr

herr_t HE5_PTreadattr(hid_t *pointID*, const char **attrname*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

datbuf IN: Buffer allocated to hold attribute values

Purpose Reads attribute from a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read floating point attribute with the name "ScalarFloat":

```
status = HE5_PTreadattr(pointID, "ScalarFloat", &attr_val);
```

FORTRAN integer function he5_ptreadatt(*pointid*,*attrname*,*buffer*)

integer *pointid*,*status*

character *(*) *attrname*

<valid type> *buffer*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptreadatt(pointid, "ScalarFloat", buffer)
```

Read Point Group Attribute

HE5_PTreadgrpattr

herr_t HE5_PTreadgrpattr(hid_t *pointID*, const char **attrname*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

datbuf IN: Buffer allocated to hold attribute values

Purpose Reads attribute associated with the “Data” group in a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read floating point attribute with the name "GroupFloat":

```
status = HE5_PTreadgrpattr(pointID, "GroupFloat",
&attr_val);
```

FORTTRAN integer function he5_ptreadgrpattr(*pointid*,*attrname*,*buffer*)

integer *pointid*,*status*

character *(*) *attrname*

<valid type> *buffer*(*)

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_ptreadgrpattr(pointid, "GroupFloat", buffer)
```

Read Point Level Attribute

HE5_PTreadlocattr

herr_t HE5_PTreadlocattr(hid_t *pointID*, const char **levelname*, const char **attrname*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

levelame IN: Level name

attrname IN: Attribute name

datbuf IN: Buffer allocated to hold attribute values

Purpose Reads attribute associated with a specified level in a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read floating point attribute with the name "LocalFloat" defined in the *Observations* level:

```
status = HE5_PTreadlocattr(pointID, "Observations",  
"LocalFloat", &attr_val);
```

FORTRAN integer function he5_ptreadlocattr(*pointid*,*levelname*,*attrname*,*buffer*)

integer *pointid*,*status*

character *(*) *levelname*,*attrname*

<valid type> *buffer*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptreadlocattr(pointid,  
"Observations", "LocalFloat", buffer)
```

Read Records From a Point Level

HE5_PTreadlevel

herr_t HE5_PTreadlevel(hid_t *pointID*, int *level*, HE5_CmpDTSinfo **inStruct*, size_t **size*, void **buffer*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach
level IN: Level to read (0-based)
inStruct IN: C-data structure containing information about specified level.
size_t IN: Size (in bytes) of data structure to read data to.
buffer OUT: Buffer to store data

Purpose Reads data from a point level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or level number.

Description This routine reads data from the specified fields and records of a single level in a point. An appropriate read buffer must be defined by the user.

Example In this example we read records from the first level in the point referred to by the point ID, *pointID1*. User should define data structure to store the output data, first. Suppose the user defined data structure to read the output data to is "Sensor".

```
CmpDTSinfo lev0_info;  
CmpDTSinfo input_info;  
Sensor *buffer;  
  
/* Get all necessary information about level first */  
status = HE5_Ptlevelinfo(pointID1, 0, &lev0_info);  
/* Set up input data structure and calculate the data size */  
nrecs = HE5_Ptnrecs(pointID1, 0);  
buffer = (Sensor *)calloc(nrecs, sizeof(Sensor));  
status = HE5_PTreadlevel(pointID1, 0, &lev0_info, datasize,  
buffer);
```

FORTRAN See Example 4 from Section 7.1.1.2 of Volume 1 (Overview of Examples).

Return Data Type Information for a Level

HE5_PTinqdatatype

herr_t HE5_PTinqdatatype(hid_t *pointID*, const char **levelname*, const char **attrname*, int *fieldgroup*, hid_t **datatype*, H5T_class_t **classid*, H5T_order_t **order*, size_t **size*)

<i>pointID</i>	IN:	Point ID returned by HE5_PTcreate or HE5_PTattach
<i>levelname</i>	IN:	Level name
<i>attrname</i>	IN:	Attribute name
<i>fieldgroup</i>	IN:	Field group flag: HE5_HDFE_DATAGROUP - 1 HE5_HDFE_ATTRGROUP - 2 HE5_HDFE_GRPATTRGROUP - 3 HE5_HDFE_LOCATTRGROUP - 4
<i>datatype</i>	OUT:	Data type ID
<i>classID</i>	OUT:	Data type class ID
<i>order</i>	OUT:	Data type byte order
<i>size</i>	OUT:	Data type size (in bytes)
Purpose		Returns data type information about specified level in point.
Return value		Returns size in bytes of specified fields if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or level name.
Description		This routine returns information about level data in a point.
Example		In this example we return the data type information for the <i>Observations</i> level in the point defined in the <i>HE5_PTdeflevel</i> routine. <pre>status = HE5_PTinqdatatype(pointID, "Observations", NULL, fieldgroup, &datatype, &classid, &order, &size);</pre>
FORTRAN		integer function he5_ptinqdatatype(<i>pointid</i> , <i>levelname</i> , <i>attrname</i> , <i>fldgrp</i> , <i>dtype</i> , <i>classid</i> , <i>order</i> , <i>size</i>)

integer *pointid,status*

integer *dtype,classid,order*

integer*4 *size*

character *(*) *levelname*

integer *HE5_HDFE_DATAGROUP*

parameter (*HE5_HDFE_DATAGROUP=1*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ptinqdatatype(pointid1, "Observations", " ",  
dtype, classid, order, size)
```

Update Records in a Point Structure

HE5_PTupdatelevel

herr_t HE5_PTupdatelevel(hid_t *pointID*, int *level*, char* *fieldlist*, hsize_t *nrec*,
hssize_t *recs*[], void **data*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Level to update (0-based)

fieldlist IN: List of fields to update

nrec IN: Number of records to update

recs IN: Record number of records to update (0 - based)

data IN: Data buffer to be written

Purpose Updates (corrects) data to a point level.

NOTE: Currently updating of a whole record is supported.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or unknown fieldname.

Description This routine updates the specified fields and records of a single level.

Example In this example we update records 0, 2, and 3 for the field *Concentration* in first level in the point referred to by the point ID, *pointID1*.

```
hsize_t recs[3] = {0,2,3};
```

```
/* Fill Data Buffer */
```

```
status = HE5_PTupdatelevel(pointID1, 0, "Concentration", 3,  
recs, datbuf);
```

The user may update a single record or all records .

FORTRAN See Example 5 from Section 7.1.1.2 of Volume 1 (Overview of Examples).

Write/Update Point Attribute

HE5_PTwriteattr

herr_HE5_PTwriteattr(hid_t *pointID*, const char **attrname*, int *ntype*, hsize_t *count*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

ntype IN: Number type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates attribute in a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.

Example In this example, we write a floating point attribute with the name "ScalarFloat" and the value 3.14:

```
attr_val = 3.14;

status = HE5_PTwriteattr(pointid, "ScalarFloat",
H5T_NATIVE_FLOAT, 1, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;

status = HE5_PTwriteattr(pointid, "ScalarFloat",
H5T_NATIVE_FLOAT, 1, &attr_val);
```

FORTTRAN integer function he5_ptwriteattr(*pointid*,*attrname*,*ntype*,*count*,*buffer*)
integer *pointid*,*status*,*ntype*

character *(*) *attrname*

integer*4 *count*

<valid type> *buffer(*)*

integer *HE5_HDFE_NATIVE_FLOAT*

parameter (*HE5_HDFE_NATIVE_FLOAT=1*)

The equivalent *FORTRAN* code for the example above is:

```
count = 1
```

```
status = he5_ptwriteattr(pointid, "ScalarFloat",  
HE5_HDFE_NATIVE_FLOAT, count, buffer)
```

Write/Update Point Group Attribute

HE5_PTwritegrpattr

herr_HE5_PTwritegrpattr(hid_t *pointID*, const char **attrname*, int *ntype*, hsize_t *count*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

attrname IN: Attribute name

ntype IN: Number type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates attribute associated with the "Data" group in a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.

Example In this example, we write a floating point group attribute with the name "GroupFloat" and the value 3.14:

```
attr_val = 3.14;

status = HE5_PTwritegrpattr(pointid, "GroupFloat",
H5T_NATIVE_FLOAT, 1, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;

status = HE5_PTwritegrpattr(pointid, "GroupFloat",
H5T_NATIVE_FLOAT, 1, &attr_val);
```

FORTTRAN integer function he5_ptwritegrpattr(*pointid*,*attrname*,*ntype*,*count*,*buffer*)
integer *pointid*,*status*,*ntype*

character *(*) *attrname*

integer*4 *count*

<valid type> *buffer(*)*

integer *HE5_HDFE_NATIVE_FLOAT*

parameter (*HE5_HDFE_NATIVE_FLOAT=1*)

The equivalent *FORTRAN* code for the example above is:

```
count = 1
```

```
status = he5_ptwritegrpattr(pointid, "GroupFloat",  
HE5_HDFE_NATIVE_FLOAT, count, buffer)
```

Write New Records to a Point Level

HE5_PTwritelevel

herr_t HE5_PTwritelevel(hid_t *pointID*, int *level*, hsize_t *nrec*[], size_t **size*, void **data*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

level IN: Level to write (0-based)

nrec IN: Number of records to write

size IN: Data size (bytes) to write

data IN: Data buffer to be written to the level

Purpose Writes (appends) new records to a point level.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or level number.

Description This routine writes (appends) full records to a level. The data buffer should be represented by the array of C-data type structures. The structure type should be consistent with that used in *HE5_PTdeflevel()*.

Example In this example we write 5 records to the first level in the point referred to by the point ID, *pointID1*.

```
/* Fill Data Buffer */  
  
/* Calculate the data size (bytes) */  
  
status = HE5_PTwritelevel(pointID1, 0, 5, datasize, datbuf);
```

FORTTRAN See Example 3 from Section 7.1.1.2 of Volume 1 (Overview of Examples).

Write/Update Point Level Attribute

HE5_PT writelocattr

herr_HE5_PT writelocattr(hid_t *pointID*, const char **levelname*, const char **attrname*, int *ntype*, hsize_t *count*, void **datbuf*)

pointID IN: Point ID returned by HE5_PTcreate or HE5_PTattach

levelname IN: Level name

attrname IN: Attribute name

ntype IN: Number type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates attribute associated with a specified level in a point.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point ID or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.

Example In this example, we write a floating point attribute with the name "LocalFloat" and the value 3.14 associated with the level "Observations":

```
attr_val = 3.14;
```

```
status = HE5_PT writelocattr(pointid, "Observations",  
"LocalFloat", H5T_NATIVE_FLOAT, 1, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;
```

```
status = HE5_PT writelocattr(pointid, "Observations",  
"LocalFloat", H5T_NATIVE_FLOAT, 1, &attr_val);
```

FORTRAN integer function
he5_ptwritelocattr(*pointid*,*levelname*,*attrname*,*ntype*,*count*,*buffer*)

integer *pointid,status,ntype*

character *(*) *attrname,levelname*

integer*4 *count*

<valid type> *buffer(*)*

integer *HE5_HDFE_NATIVE_FLOAT*

parameter (*HE5_HDFE_NATIVE_FLOAT=1*)

The equivalent *FORTRAN* code for the example above is:

```
count = 1
```

```
status = he5_ptwritelocattr(pointid, "Observations",  
"LocalFloat", HE5_HDFE_NATIVE_FLOAT, count, buffer)
```

2.1.2 Swath Interface Functions

This section contains an alphabetical listing of all the functions in the Swath interface. The functions are alphabetized based on their C-language names.

Return Information About an Alias

HE5_SWaliasinfo

herr_t HE5_SWaliasinfo(hid_t *swathID*, int *fldgroup*, const char **aliasname*, int **length*, char **buffer*)

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fldgroup</i>	IN: Field group flag
<i>aliasname</i>	IN: Name of alias to retrieve information about
<i>length</i>	OUT: Size of buffer in bytes
<i>buffer</i>	OUT: Buffer with original field name
Purpose	Return information about an alias
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	Creates aliases that can be used to refer to a Swath data field in addition to the name of the field.
Example	<p>In this example, we create an alias for the data field <i>Temperature</i>.</p> <pre>status = HE5_SWaliasinfo(swathID, HE5_HDFE_DATAGROUP, aliasname, length, NULL); namebuffer = (char *)calloc(length + 1, sizeof(char)); status = HE5_SWaliasinfo(swathID, HE5_HDFE_DATAGROUP, aliasname, length, namebuffer);</pre>
FORTTRAN	<pre>integer function he5_swaliasinfo (<i>swathid</i>, <i>fldgroup</i>, <i>aliasname</i>, <i>length</i>, <i>buffer</i>) integer <i>swathid</i>,<i>status</i> character*(*) <i>fldgroup</i> character*(*) <i>aliasname</i> integer*(*) <i>length</i> character*(*) <i>buffer</i></pre>

The equivalent *FORTTRAN* code for the first example above is:

```
aliaslist = "temps 0 to 30"

status = he5_swaliasinfo(swathid, "Temperature", aliaslist,
length, buffer)
```

Attach to an Existing Swath Structure

HE5_SWattach

hid_t HE5_SWattach(hid_t *fid*, const char **swathname*)

fid IN: Swath file ID returned by HE5_SWopen

swathname IN: Name of swath to be attached

Purpose Attaches to an existing swath within the file.

Return value Returns the swath handle (swathID) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath file id or swath name.

Description This routine attaches to the swath using the *swathname* parameter as the identifier.

Example In this example, we attach to the previously created swath, "ExampleSwath", within the HDF-EOS file, *Swath.he5*, referred to by the handle, *fid*:

```
swathID = HE5_SWattach(fid, "ExampleSwath");
```

The swath can then be referenced by subsequent routines using the handle, *swathID*.

FORTRAN integer function he5_swattach(*fid*,*swathname*)

integer *fid*

character*(*) *swathname*

The equivalent *FORTRAN* code for the example above is:

```
swathid = he5_swattach(fid, "ExampleSwath")
```

Return Information About a Swath Attribute

HE5_SWattrinfo

herr_t HE5_SWattrinfo(hid_t *swathID*, const char **attrname*, H5T_class_t **ntype*,
hsize_t **count*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrname IN: Attribute name

ntype OUT: Number type of attribute

count OUT: Number of total bytes in attribute

Purpose Returns information about a swath attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of a swath attribute.

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_SWattrinfo(swathID, "ScalarFloat",&nt,&count);
```

The *nt* variable will have the value 1 and *count* will have the value 4.

FORTRAN integer function he5_swattrinfo(*swathid*, *attrname*, *ntype*, *count*)

integer *swathid*

character*(*) *attrname*

integer *ntype*

integer*4 *count*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swattrinfo(swathid, "ScalarFloat",ntype,count)
```

Close an HDF-EOS File

HE5_SWclose

herr_t HE5_SWclose(hid_t *fid*)

fid IN: Swath file ID returned by HE5_SWopen

Purpose Closes file.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine closes the HDF-EOS Swath file.

Example

```
status = HE5_SWclose(fid);
```

FORTRAN integer function he5_swclose(*fid*)

integer *fid*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swclose(fid)
```

Retreive Compression Information for Field

HE5_SWcompinfo

herr_t HE5_SWcompinfo(hid_t *swathID*, const char **fieldname*, int **compcode*,
int *compparm*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Fieldname

compcode OUT: HDF compression code

compparm OUT: Compression parameters

Purpose Retrieves compression information about a field.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine returns the compression code and compression parameters for a given field.

Example To retrieve the compression information about the *Opacity* field defined in the *HE5_SWdefcomp* function:

```
status = HE5_SWcompinfo(swathID, "Opacity", &compcode,  
compparm);
```

The *compcode* parameter will be set to 4 and *compparm*[0] to 5.

FORTRAN integer function he5_swcompinfo(*gridid*,*fieldname* *compcode*, *compparm*)

integer *swathid*

character*(*) *fieldname*

integer *compcode*

integer *compparm*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swcompinfo(swathid, 'Opacity', compcode,  
compparm)
```

The *compcode* parameter will be set to 4 and *compparm*(1) to 5.

Create a New Swath Structure

HE5_SWcreate

hid_t HE5_SWcreate(hid_t *fid*, const char **swathname*)

fid IN: Swath file ID returned by HE5_SWopen

swathname IN: Name of swath to be created

Purpose Creates a swath within the file.

Return value Returns the swath handle (*swathID*) if successful or FAIL (-1) otherwise.

Description The swath is created as a Group within the HDF-EOS file with the name *swathname*.

Example In this example, we create a new swath structure, *ExampleSwath*, in the previously created file, *Swath.he5*.

```
swathID = HE5_SWcreate(fid, "ExampleSwath");
```

The swath structure is referenced by subsequent routines using the handle, *swathID*.

FORTTRAN integer function he5_swcreate(*fid*,*swathname*)

```
integer      fid
```

```
character*(*) swathname
```

The equivalent *FORTTRAN* code for the example above is:

```
swathid = he5_swcreate(fid, "ExampleSwath")
```

Define a Longitude-Latitude Box Region for a Swath

HE5_SWdefboxregion

hid_t HE5_SWdefboxregion(hid_t *swathID*, double *cornerlon*[], double *cornerlat*[], int *mode*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

cornerlon IN: Longitude in decimal degrees of box corners

cornerlat IN: Latitude in decimal degrees of box corners

mode IN: Cross Track inclusion mode

Purpose Defines a longitude-latitude box region for a swath.

Return value Returns the swath region ID if successful or FAIL (-1) otherwise.

Description This routine defines a longitude-latitude box region for a swath. It returns a swath region ID which is used by the *HE5_SWextractregion* routine to read all the entries of a data field within the region. A cross track is within a region if 1) its midpoint is within the longitude-latitude "box" (HE5_HDFE_MIDPOINT), or 2) either of its endpoints is within the longitude-latitude "box" (HE5_HDFE_ENDPOINT), or 3) any point of the cross track is within the longitude-latitude "box" (HE5_HDFE_ANYPOINT), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the region even though a particular element of the cross track might be outside the region. The swath structure must have both *Longitude* and *Latitude* (or *Colatitude*) fields defined.

Example In this example, we define a region bounded by the 3 degrees longitude, 5 degrees latitude and 7 degrees longitude, 12 degrees latitude. We will consider a cross track to be within the region if its midpoint is within the region.

```
cornerlon[0] = 3.;
```

```
cornerlat[0] = 5.;
```

```
cornerlon[1] = 7.;
```

```
cornerlat[1] = 12.;
```

```
regionID = HE5_SWdefboxregion(swathID, cornerlon, cornerlat,  
HE5_HDFE_MIDPOINT);
```

FORTTRAN integer function `he5_swdefboxreg(swathid, cornerlon, cornerlat, mode)`

integer *swathid*

real*8 *cornerlon*(*)

real*8 *cornerlat*(*)

integer *mode*

The equivalent *FORTTRAN* code for the example above is:

```
parameter (HE5_HDFE_MIDPOINT=0)
cornerlon(1) = 3.
cornerlat(1) = 5.
cornerlon(2) = 7.
cornerlat(2) = 12.
regionid = he5_swdefboxreg(swathid, cornerlon, cornerlat,
HE5_HDFE_MIDPOINT)
```

Define Chunking Parameters

HE5_SWdefchunk

herr_t HE5_SWdefchunk(hid_t *swathID*, int *chunk_rank*, const hsize_t
**chunk_dims*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

chunk_rank IN: The number of chunk dimensions

chunk_dims IN: Chunk dimensions

Purpose Defines chunking for subsequent field definitions

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description This routine defines the chunking dimensions for fields defined following this function call, analogous to the procedure for setting the field compression scheme using *HE5_SWdefcomp*. The number of tile dimensions and subsequent field dimensions must be the same.

Example We will define chunking for a two-dimensional field of size
2400 x 3600 .

```
chunk_dims[0] = 100;
```

```
chunk_dims[1] = 360;
```

```
status = HE5_SWdefchunk(swathID, 2, chunk_dims);
```

FORTRAN integer function he5_swdefchunk(*swathid*, *chunk_rank*, *chunk_dims*)

integer *swathid*

integer *chunk_rank*

integer*4 *chunk_dims*(*)

The equivalent *FORTRAN* code for the example above is:

```
chunk_dims(1) = 360
```

```
chunk_dims(2) = 100
```

```
chunk_rank = 2
```

```
status = he5_swdefchunk(swathid, chunk_rank, chunk_dims)
```

Define Compression with Data Chunking

HE5_SWdefcomchunk

herr_t HE5_SWdefcomchunk(hid_t *swathID*, int *compcode*, int **compparm*, int *ndims*, const hsize **dim*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

compcode IN: Compression method flag

compparm IN: Array of compression parameters

ndims IN: Rank of a field to compress

dim IN: Array of sizes of chunk

Purpose Compress the data field

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This function allows the user to set compression for a data field with automatic chunking

Example In this example, we set (DEFLATE) compression for a field that is defined right after this call

```
ndims      = 2
compcode   = 4;
compparm[0] = 6;
dim[0]     = 100;
dim[1]     = 200;

status = HE5_SWdefcomchunk(swathID, compcode, compparm,
ndims, dim);
```

FORTTRAN integer function he5_swdefcomch(swathid,compcode, compparm,
ndims,dim)

```
integer    swathid
integer    compcode
integer    compparm(*)
integer    ndims
integer*4  dim(*)
```

The equivalent *FORTRAN* code for the example above is:

```
compcode      = 4
compparm(1)  = 6
ndims         = 2
dim(1)        = 200
dim(2)        = 100
status = he5_swdefcomch(swathid, compcode, compparm, ndims,
dim)
```

Set Swath Field Compression

HE5_SWdefcomp

herr_t HE5_SWdefcomp(hid_t *swathID*, int *compcode*, int **compparm*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

compcode IN: HDF compression code

compparm IN: Compression parameters (if applicable)

Note: Only deflate compression is available in this release.

Purpose Sets the field compression for all subsequent field definitions.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine sets the HDF field compression for subsequent swath field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported is: deflate (gzip) (HE5_HDFE_COMP_DEFLATE=4) and no compression (HE5_HDFE_COMP_NONE = 0, the default). Deflate compression requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression. Compressed fields are written using the standard *HE5_SWwritefield* routine, however, the entire field must be written in a single call. Any portion of a compressed field can then be accessed with the *HE5_SWreadfield* routine. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of the compression schemes and parameters.

Example Suppose we wish to compress the *Pressure* using run length encoding, the *Opacity* field using deflate compression, the *Spectra* field with skipping Huffman compression, and use no compression for the *Temperature* field.

```
status = HE5_SWdefcomp(swathID, HE5_HDFE_COMP_DEFLATE,
NULL);
```

```
status = HE5_SWdefdatafield(swathID, "Pressure",
"Track,Xtrack", NULL, H5T_NATIVE_FLOAT, 0);
```

```
compparm[0] = 5;
```

```
status = HE5_SWdefdatafield(swathID, "Opacity",
"Track,Xtrack", NULL, H5T_NATIVE_FLOAT, 0);
```

```

status = HE5_SWdefdatafield(swathID, "Spectra",
"Bands,Track,Xtrack", NULL, H5T_NATIVE_FLOAT, HDFE_NOMERGE);
status = HE5_SWdefcomp(swathID, HE5_HDFE_COMP_NONE, NULL);
status = HE5_SWdefdatafield(swathID, "Temperature",
"Track,Xtrack", NULL, H5T_NATIVE_FLOAT, 0);

```

Note that the HE5_HDFE_AUTOMERGE/MERGE parameter is ignored in the *Temperature* field definition.

FORTRAN integer function he5_swdefcomp(*swathid*, *compcode*, *compparm*)

```

integer      swathid
integer      compcode
integer      compparm(*)

```

The equivalent *FORTRAN* code for the example above is:

```

parameter (HE5_HDFE_NATIVE_FLOAT=1)
parameter (HE5_HDFE_COMP_NONE=0)
parameter (HE5_HDFE_COMP_DEFLATE=4)
integer    compparm(5)
status = he5_swdefcomp(swathid, HE5_HDFE_COMP_DEFLATE,
compparm);
status = he5_swdefdfld(swathid, "Pressure", "Xtrack,Track",
" ", HE5_HDFE_NATIVE_FLOAT, 0);
compparm(1) = 5
status = he5_swdefdfld(swathid, "Opacity", "Xtrack,Track", "
", HE5_HDFE_NATIVE_FLOAT, 0);
status = he5_swdefdfld(swathid, "Spectra", "Xtrack,
Track,Bands", " ", HE5_HDFE_NATIVE_FLOAT, 0)
status = he5_swdefcomp(swathid, HE5_HDFE_COMP_NONE,
compparm)
status = he5_swdefdfld(swathid, "Temperature",
"Xtrack,Track", " ", HE5_HDFE_NATIVE_FLOAT, 0)

```

Define a New Data Field within a Swath

HE5_SWdefdatafield

herr_t HE5_SWdefdatafield(hid_t *swathID*, const char **fieldname*, char **dimlist*, char **maxdimlist*, hid_t *ntype*, int *merge*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fieldname</i>	IN:	Name of field to be defined
<i>dimlist</i>	IN:	The list of data dimensions defining the field
<i>maxdimlist</i>	IN:	The list of maximum data dimensions defining the field
<i>ntype</i>	IN:	The number type of the data stored in the field
<i>merge</i>	IN:	Merge code (HE5_HDFE_NOMERGE (0) - no merge, HE5_HDFE_AUTOMERGE (1) -merge)

Note: Merging is not supported in this release of the library. There are three illegal characters for field names: “/”, “;”, “,”

Purpose	Defines a new data field within the swath.
Return value	Returns SUCCEEDED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.
Description	This routine defines geolocation fields to be stored in the swath. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in <i>C</i> order, that is, the last dimension is incremented first. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, numbertype.
Example	<p>In this example, we define a three dimensional data field named <i>Spectra</i> with dimensions <i>Bands</i>, <i>DataTrack</i>, and <i>DataXtrack</i>:</p> <pre>status = HE5_SWdefdatafield(swathID, "Spectra", "Bands,DataTrack,DataXtrack", " ", H5T_NATIVE_FLOAT, 0);</pre> <p>Note: To assure that the fields defined by <i>HE5_SWdefdatafield</i> are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.</p>
FORTRAN	integer function he5_swdefdfd(<i>swathid</i> , <i>fieldname</i> , <i>dimlist</i> , <i>maxdimlist</i> , <i>ntype</i> , <i>merge</i>)

integer *swathid*
character*(*) *fieldname*
character*(*) *dimlist*
character*(*) *maxdimlist*
integer *ntype*
integer *merge*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)  
parameter (HE5_HDFE_AUTOMERGE=1)  
  
status = he5_swdefdfld(swathid, "Spectra", "DataXtrack,  
DataTrack, Bands", " ", HE5_HDFE_NATIVE_FLOAT, 0)
```

Define a New Dimension within a Swath

HE5_SWdefdim

herr_t HE5_SWdefdim(hid_t *swathID*, char **dimname*, hsize_t *dim*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

dimname IN: Name of dimension to be defined

dim IN: The size of the dimension

**Note: There are three illegal characters for dimension names: “/”,
”,”,””**

Purpose Defines a new dimension within the swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is an improper swath ID.

Description This routine defines dimensions that are used by the field definition routines (described subsequently) to establish the size of the field.

Example In this example, we define a track geolocation dimension, *GeoTrack*, of size 2000, a cross track dimension, *GeoXtrack*, of size 1000 and two corresponding data dimensions with twice the resolution of the geolocation dimensions:

```
status = HE5_SWdefdim(swathID, "GeoTrack", 2000);  
status = HE5_SWdefdim(swathID, "GeoXtrack", 1000);  
status = HE5_SWdefdim(swathID, "DataTrack", 4000);  
status = HE5_SWdefdim(swathID, "DataXtrack", 2000);  
status = HE5_SWdefdim(swathID, "Bands", 5);
```

To specify an unlimited dimension which can be used to define an appendable array, the dimension value should be set to -1 or equivalently, *H5S_UNLIMITED*:

```
status = HE5_SWdefdim(swathID, "Unlim", H5S_UNLIMITED);
```

FORTTRAN integer function he5_swdefdim(*swathid*,*dimname*,*dim*)

```
integer      swathid  
character*(*) dimname  
integer*4    dim
```

The equivalent *FORTTRAN* code for the first example above is:

```
dim      = 2000
status = he5_swdefdim(swathid, "GeoTrack", dim)
```

The equivalent *FORTRAN* code for the unlimited dimension example above is:

```
parameter (H5S_UNLIMITED=-1)

status = he5_swdefdim(swathid, "Unlim", H5S_UNLIMITED)
```

Define Mapping between Geolocation and Data Dimensions

HE5_SWdefdimmap

herr_t HE5_SWdefdimmap(hid_t *swathID*, char **geodim*, char **datadim*, hsize_t *offset*, hsize_t *increment*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>geodim</i>	IN:	Geolocation dimension name
<i>datadim</i>	IN:	Data dimension name
<i>offset</i>	IN:	The offset of the geolocation dimension with respect to the data dimension
<i>increment</i>	IN:	The increment of the geolocation dimension with respect to the data dimension

Purpose Defines monotonic mapping between the geolocation and data dimensions.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is incorrect geolocation or data dimension name.

Description Typically the geolocation and data dimensions are of different size (resolution). This routine established the relation between the two where the offset gives the index of the data element (0-based) corresponding to the first geolocation element and the increment gives the number of data elements to skip for each geolocation element. If the geolocation dimension begins "before" the data dimension, then the offset is negative. Similarly, if the geolocation dimension has higher resolution than the data dimension, then the increment is negative.

Example In this example, we establish that (1) the first element of the *GeoTrack* dimension corresponds to the first element of the *DataTrack* dimension and the data dimension has twice the resolution as the geolocation dimension, and (2) the first element of the *GeoXtrack* dimension corresponds to the second element of the *DataTrack* dimension and the data dimension has twice the resolution as the geolocation dimension:

```
status = HE5_SWdefdimmap(swathID, "GeoTrack", "DataTrack",  
0, 2);
```

```
status = HE5_SWdefdimmap(swathID, "GeoXtrack", "DataXtrack",  
1, 2);
```

FORTTRAN integer function he5_swdefmap(*swathid,geodim,datadim,offset,increment*)
integer *swathid*
character*(*) *geodim*
character*(*) *datadim*
integer*4 *offset*
integer*4 *increment*

The equivalent *FORTTRAN* code for the second example above is:

```
offset = 0  
increment = 2  
status = he5_swdefmap(swathid, "GeoTrack", "DataTrack",  
offset, increment)  
offset = 1  
increment = 2  
status=he5_swdefmap(swathid, "GeoXtrack", "DataXtrack", offset,  
increment)
```

Define a new Geolocation Field within a Swath

HE5_SWdefgeofield

herr_t HE5_SWdefgeofield(hid_t *swathID*, const char **fieldname*, char **dimlist*, char **maxdimlist*, hid_t *ntype*, int *merge*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fieldname</i>	IN:	Name of field to be defined
<i>dimlist</i>	IN:	The list of geolocation dimensions defining the field
<i>maxdimlist</i>	IN:	The maximum dimension list of geolocation dimensions defining the field
<i>ntype</i>	IN:	The number type of the data stored in the field
<i>merge</i>	IN:	Merge code (HE5_HDFE_NOMERGE (0) - no merge, HE5_HDFE_AUTOMERGE(1) - merge)

Note: Merging is not supported in this release of the library. There are three illegal characters for field names: “/”, “;”, “,”

Purpose	Defines a new geolocation field within the swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.
Description	This routine defines geolocation fields to be stored in the swath. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in <i>C</i> order, that is, the last dimension is incremented first. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, <i>numbertype</i> . Two and three dimensional fields will be merged into a single three-dimensional object if the last two dimensions (in <i>C</i> order are equal). If the merge code for a field is set to 0, the API will not attempt to merge it with other fields. Fields using the unlimited dimension will not be merged.
Example	In this example, we define the geolocation fields, <i>Longitude</i> and <i>Latitude</i> with dimensions <i>GeoTrack</i> and <i>GeoXtrack</i> and containing 4 byte floating point numbers. We allow these fields to be merged into a single object:

```
status = HE5_SWdefgeofield(swathID, "Longitude",  
                           "GeoTrack,GeoXtrack", NULL, H5T_NATIVE_FLOAT, 0);
```

```

status = HE5_SWdefgeofield(swathID, "Latitude",
    "GeoTrack,GeoXtrack", NULL, H5T_NATIVE_FLOAT,
HE5_HDFE_NOMERGE);

```

Note: To assure that the fields defined by *HE5_SWdefgeofield* are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.

```

FORTRAN integer function he5_swdefgfld(swathid, fieldname, dimlist, maxdimlist,
ntype, merge)
integer      swathid
character*(*) fieldname
character*(*) dimlist
character*(*) maxdimlist
integer      ntype
integer      merge

```

The equivalent *FORTRAN* code for the first example above is:

```

parameter (HE5_HDFE_NATIVE_FLOAT=1)
parameter (HE5_HDFE_NOMERGE=0)

status=he5_swdefgfld(swathid, "Longitude", "GeoXtrack,GeoTrack",
" ", " ", HE5_HDFE_NATIVE_FLOAT, HE5_HDFE_NOMERGE)

```

The dimensions are entered in *FORTRAN* order with the first dimension incremented first.

Define Indexed Mapping between Geolocation and Data Dimension

HE5_SWdefidxmap

herr_t HE5_SWdefidxmap(hid_t *swathID*, char **geodim*, char **datadim*, long *index[]*),

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
geodim IN: Geolocation dimension name
datadim IN: Data dimension name
index IN: The array containing the indices of the data dimension to which each geolocation element corresponds.

Purpose Defines a non-regular mapping between the geolocation and data dimension.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is incorrect geolocation or data dimension name.

Description If there does not exist a regular (linear) mapping between a geolocation and data dimension, then the mapping must be made explicit. Each element of the *index* array, whose dimension is given by the geolocation size, contains the element number (0-based) of the corresponding data dimension.

Example In this example, we consider the (simple) case of a geolocation dimension, *IdxGeo* of size 5 and a data dimension *IdxData* of size 8.

```
long index[5] = {0,2,3,6,7};  
status = HE5_SWdefidxmap(swathID, "IdxGeo", "IdxData",  
index);
```

In this case the 0th element of *IdxGeo* will correspond to the 0th element of *IdxData*, the 1st element of *IdxGeo* to the 2nd element of *IdxData*, etc.

FORTTRAN integer function he5_swdefimap(*swathid*, *geodim*, *datadim*, *index*)

```
integer      swathid  
character(*) geodim  
character(*) datadim  
integer*4    index (*)
```

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_swdefimap(swathid, "IdxGeo", "IdxData", index)
```

Define a Time Period of Interest

HE5_SWdeftimeperiod

hid_t HE5_SWdeftimeperiod(hid_t *swathID*, double *starttime* , double *stoptime*, int *mode*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>starttime</i>	IN:	Start time of period
<i>stoptime</i>	IN:	Stop time of period
<i>mode</i>	IN:	Cross Track inclusion mode
Purpose		Defines a time period for a swath.
Return value		Returns the swath period ID if successful or FAIL (-1) otherwise.
Description		This routine defines a time period for a swath. It returns a swath period ID which is used by the <i>HE5_SWextractperiod</i> routine to read all the entries of a data field within the time period. A cross track is within a time period if 1) its midpoint is within the time period "box", or 2) either of its endpoints is within the time period "box", or 3) any point of the cross track is within the time period "box", depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the time period even though a particular element of the cross track might be outside the time period. The swath structure must have the <i>Time</i> field defined

Example In this example, we define a time period with a start time of 35232487.2 and a stop time of 36609898.1. We will consider a cross track to be within the time period if either one of the time values at the endpoints of a cross track are within the time period.

```
starttime = 35232487.2;
stoptime = 36609898.1;

periodID = HE5_SWdeftimeperiod(swathID, starttime, stoptime,
HE5_HDFE_ENDPOINT);
```

FORTRAN integer function he5_swdeftmeper(*swathid*, *starttime*, *stoptime*, *mode*)
integer *swathid*
real*8 *starttime*
real*8 *stoptime*
integer *mode*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_ENDPOINT=1)
starttime = 35232487.2
stoptime = 36609898.1
periodID = he5_swdeftmeper(swathID, starttime, stoptime,
HE5_HDFE_ENDPOINT)
```

Define a Vertical Subset Region

HE5_SWdefvrtregion

hid_t HE5_SWdefvrtregion(hid_t *swathID*, hid_t *regionID*, char **vertObj*, double *range*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

regionID IN: Region (or period) id from previous subset call

vertObj IN: Dimension or field to subset by

range IN: Minimum and maximum range for subset

Purpose Subsets on a **monotonic** field or contiguous elements of a dimension.

Return value Returns the swath region ID if successful or FAIL (-1) otherwise.

Description Whereas the *HE5_SWdefboxregion* and *HE5_SWdeftimeperiod* routines perform subsetting along the “Track” dimension, this routine allows the user to subset along any dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range(case 2) . In the second case, the field must be one-dimensional and the values must be **monotonic** (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this routine, the second option is restricted to fields with number type: INT, LONG, FLOAT, DOUBLE.) This routine may be called after *HE5_SWdefboxregion* or *HE5_SWdeftimeperiod* to provide both geographic or time and “vertical” subsetting . In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the region ID to HE5_HDFE_NOPREVSUB (-1).

This routine may be called up to eight times with the same region ID. In this way a region can be subsetted along a number of dimensions.

The *HE5_SWregioninfo* and *HE5_SWextractregion* routines work as before, however because there is no mapping performed between geolocation dimensions and data dimensions the field to be subsetted, (the field specified in the call to *HE5_SWregioninfo* and *HE5_SWextractregion*) must contain the dimension used explicitly in the call to *HE5_SWdefvrtregion* (case 1) or the dimension of the one-dimensional field (case 2).

Example

Suppose we have a field called *Pressure* of dimension *Height* (= 10) whose values increase from 100 to 1000. If we desire all the elements with values between 500 and 800, we make the call:

```
range[0] = 500.;
range[1] = 800.;
regionID = HE5_SWdefvrtregion(swathID, HE5_HDFE_NOPREVSUB,
"Pressure", range);
```

The routine determines the elements in the *Height* dimension which correspond to the values of the *Pressure* field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the *Height* dimension, the call would be:

```
range[0] = 2;
range[1] = 5;
regionID = HE5_SWdefvrtregion(swathID, HE5_HDFE_NOPREVSUB,
"DIM:Height", range);
```

The "DIM:" prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field.

In this example, any field to be subsetted must contain the *Height* dimension.

If a previous subset region or period was defined with id, *subsetID*, that we wish to refine further with the vertical subsetting defined above we make the call:

```
regionID = HE5_SWdefvrtregion(swathID, subsetID, "Pressure",
range);
```

The return value, *regionID* is set equal to *subsetID*. That is, the subset region is modified rather than a new one created.

We can further refine the subset region with another call to the routine:

```
freq[0] = 1540.3;
freq[1] = 1652.8;
regionID = HE5_SWdefvrtregion(swathID, regionID,
"FreqRange", freq);
```

FORTTRAN integer function `he5_swdefvrtreg(swathid, regionid, vertobj, range)`
integer *swathid*
integer *regionid*
character*(*) *vertobj*
real*8 *range*(*)

The equivalent *FORTTRAN* code for the examples above is:

```
parameter (HE5_HDFE_NOPREVSUB=-1)
range(1) = 500.
range(2) = 800.
regionid = he5_swdefvrtreg(swathid, HE5_HDFE_NOPREVSUB,
"Pressure", range)
```

Detach from a Swath Structure

HE5_SWdetach

herr_t HE5_SWdetach(hid_t *swathID*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

Purpose Detaches from swath interface.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine should be run before exiting from the swath file for every swath opened by *HE5_SWcreate* or *HE5_SWattach*.

Example In this example, we detach the swath structure, *ExampleSwath*:

```
status = HE5_SWdetach(swathID);
```

FORTRAN integer function he5_swdetach(swathid)

```
integer      swathid
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swdetach(swathid)
```

Retrieve Size of Specified Dimension

HE5_SWdiminfo

hsize_t HE5_SWdiminfo(hid_t *swathID*, char **dimname*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

dimname IN: Dimension name

Purpose Retrieve size of specified dimension.

Return value Size of dimension if successful or FAIL (-1) otherwise. If -1, could signify an improper swath ID or dimension name.

Description This routine retrieves the size of specified dimension.

Example In this example, we retrieve information about the dimension, "GeoTrack":

```
dimsize = HE5_SWdiminfo(swathID, "GeoTrack");
```

The return value, *dimsize*, will be equal to 2000.

FORTTRAN integer*4 function he5_swdiminfo(*swathid*,*dimname*)

integer *swathid*

character*(*) *dimname*

integer*4 *dimsize*

The equivalent *FORTTRAN* code for the example above is:

```
dimsize = he5_swdiminfo(swathid, "GeoTrack")
```

Remove an Alias for Swath Data Field

HE5_SWdropalias

herr_t HE5_SWdropalias(hid_t *swathID*, int *fldgroup*, const char **aliasname*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fldgroup IN: Field group flag

aliasname IN: Name of alias to remove

Purpose Remove an alias for Swath data field

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description Removes alias associated with a Swath data field.

Example In this example, we create and alias for the data field *Temperature*.

```
strcpy(aliasname, "temps 0 to 30");
```

```
status = HE5_SWdropalias(swathID, HE5_HDFE_DATAGROUP,  
aliasname);
```

FORTRAN integer function he5_swdropalias (*swathid*, *fldgroup*, *aliasname*)
integer *swathid*
character*(*) *fldgroup*
character*(*) *aliasname*

The equivalent *FORTRAN* code for the first example above is:

```
aliasname = "temps 0 to 30"
```

```
status = he5_swdropalias(swathid, HE5_HDFE_DATAGROUP,  
aliasname)
```

Duplicate a Region or Period

HE5_SWdupregion

hid_t HE5_SWdupregion(hid_t *regionID*)

- regionID* IN: Region or period ID returned by HE5_SWdefboxregion, HE5_SWdeftimeperiod, or HE5_SWdefvrtregion.
- Purpose Duplicates a region.
- Return value Returns new region or period ID if successful or FAIL (-1) otherwise.
- Description This routine copies the information stored in a current region or period to a new region or period and generates a new id. It is usefully when the user wishes to further subset a region (period) in multiple ways.
- Example In this example, we first subset a swath with *HE5_SWdefboxregion*, duplicate the region creating a new region ID, *regionID2*, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = HE5_SWdefboxregion(swathID, cornerlon, cornerlat,
                             HE5_HDFE_MIDPOINT);

regionID2 = HE5_SWdupregion(regionID);

regionID = HE5_SWdefvrtregion(swathID, regionID, "Pressure",
                              rangePres);

regionID2 = HE5_SWdefvrtregion(swathID, regionID2,
                              "Temperature", rangeTemp);
```

FORTRAN integer he5_swdupreg(*regionid*)

integer *regionid*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_MIDPOINT=0)

regionid = he5_swdefboxreg(swathid, cornerlon, cornerlat,
                          HE5_HDFE_MIDPOINT)

regionid2 = he5_swdupreg(regionid)

regionid = he5_swdefvrtreg(swathid, regionid, 'Pressure',
                          rangePres)

regionid2 = he5_swdefvrtreg(swathid, regionid2,
                          'Temperature', rangeTemp)
```

Read Data from a Defined Time Period

HE5_SWextractperiod

herr_t HE5_SWextractperiod(hid_t *swathID*, hid_t *periodID*, char **fieldname*, int *externalflag*, void **buffer*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

periodID IN: Period id returned by HE5_SWdeftimeperiod

fieldname IN: Field to subset

externalflag IN: External geolocation mode

buffer OUT: Data buffer

Purpose Extracts (reads) from subsetted time period.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

NOTE: External file functionality not available in this release

Description This routine reads data into the data buffer from the subsetted time period. Only complete crosstracks are extracted. If the *external_mode* flag is set to *HE5_HDFE_EXTERNAL* (1) then the geolocation fields and the data field can be in different swaths. If set to *HE5_HDFE_INTERNAL* (0), then these fields must be in the same swath structure.

Example In this example, we read data within the subsetted time period defined in *HE5_SWdeftimeperiod* from the *Spectra* field. Both the geolocation fields and the *Spectra* data field are in the same swath.

```
status = HE5_SWextractperiod(SwathID, periodID, "Spectra",  
                             HE5_HDFE_INTERNAL, datbuf);
```

FORTTRAN integer function he5_swextper(*swathID*, *periodid*, *fieldname*, *externalflag*, *buffer*)

integer *swathID*

integer *periodid*

character*(*) *fieldname*

integer *externalflag*

<valid type> *buffer*(*)

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_INTERNAL=0)

status = he5_swextper(swathid, periodid, "Spectra",
HE5_HDFE_INTERNAL, datbuf)
```

Read Data from a Geographic Region

HE5_SWextractregion

herr_t HE5_SWextractregion(hid_t *swathID*, hid_t *regionID*, char **fieldname*, int *externalflag*, void **buffer*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

regionID IN: Region ID returned by HE5_SWdefboxregion

fieldname IN: Field to subset

externalflag IN: External geolocation mode

buffer OUT: Data buffer

Purpose Extracts (reads) from subsetted region.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

NOTE: External file functionality not available in this release

Description This routine reads data into the data buffer from the subsetted region. Only complete crosstracks are extracted. If the external_mode flag is set to *HE5_HDFE_EXTERNAL* (1) then the geolocation fields and the data field can be in different swaths. If set to *HE5_HDFE_INTERNAL* (0), then these fields must be in the same swath structure.

Example In this example, we read data within the subsetted region defined in *HE5_SWdefboxregion* from the *Spectra* field. Both the geolocation fields and the *Spectra* data field are in the same swath.

```
status = HE5_SWextractregion(Swid, regionID, "Spectra",  
                             HE5_HDFE_INTERNAL, datbuf);
```

FORTRAN integer function he5_swextreg(*swathid*, *regionid*, *fieldname*, *externalflag*,
buffer)

integer *swathid*

integer *regionid*

character*(*) *fieldname*

integer *externalflag*

<valid type> *buffer*(*)

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_INTERNAL=0)
status = he5_swextreg(swathid, regionid, "Spectra",
HE5_HDFE_INTERNAL, datbuf)
```

Retrieve Information about a Swath Field

HE5_SWfieldinfo

herr_t HE5_SWfieldinfo(hid_t *swathID*, char **fieldname*, int **rank*, hsize_t *dims*[], H5T_class_t *ntype*[], char **dimlist*, char **maxdimlist*)

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fieldname</i>	IN: Fieldname
<i>rank</i>	OUT: Rank of field
<i>dims</i>	OUT: Array containing the dimension sizes of the field
<i>ntype</i>	OUT: Array containing the numbertype of the field
<i>dimlist</i>	OUT: List of dimensions in field
<i>maxdimlist</i>	OUT: List of maximum dimensions in field
Purpose	Retrieve information about a specific geolocation or data field in the swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. A typical reason for failure is the specified field does not exist.
Description	This routine retrieves information on a specific data field.
Example	<p>In this example, we retrieve information about the <i>Spectra</i> data fields:</p> <pre>status = HE5_SWfieldinfo(swathID, "Spectra", &rank, dims, numbertype, dimlist, maxdimlist);</pre> <p>The return parameters will have the following values:</p> <p><i>rank</i>=3, <i>numbertype</i>=5, <i>dims</i>[3]={5,4000,2000} and <i>dimlist</i>="Bands, DataTrack, DataXtrack"</p> <p>If one of the dimensions in the field is appendable, then the current value for that dimension will be returned in the <i>dims</i> array.</p>

FORTRAN integer function `he5_swfldinfo`(*swathid*, *fieldname*, *rank*, *dims*, *ntype*,
dimlist, *maxdimlist*)

integer *swathid*

character*(*) *fieldname*

integer *rank*

integer*4 *dims*(*)

integer *ntype*(*)

character*(*) *dimlist*

character*(*) *maxdimlist*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swfldinfo(swathid, "Spectra", rank, dims,
numbertype, dimlist, maxdimlist)
```

The return parameters will have the following values:

rank=3, *numbertype*=5, *dims*[3]={2000,4000,5} and
dimlist="DataXtrack, DataTrack,Bands"

Note that the dimensions array and dimension list are in FORTRAN order.

Rename Swath Data Field

HE5_SWfldrename

herr_t HE5_SWfldrename(hid_t *swathID*, char **oldfieldname*, const char **newfieldname*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

oldfieldname IN: Current name of field

newfieldname IN: New name of field

Purpose Rename swath data field

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This function allows the user to change the name of a field. This is useful in case the user would want to update the data field to reflect a version change in the calibration of a data field and show that in the name of the field.

Example In this example, we create an alias for the data field *Temperature*.

```
strcpy(newfieldname, "temps 0 to 30");
```

```
status = HE5_SWfldrename(swathID, "Temperature",  
newfieldname);
```

FORTRAN integer function he5_swfldrename (*swathid*, *oldfieldname*, *newfieldname*)
integer *swathid*
character*(*) *oldfieldname*
character*(*) *newfieldname*

The equivalent *FORTRAN* code for the first example above is:

```
newfieldname = "temps 0 to 30"
```

```
status = he5_swfldrename(swathid, "Temperature",  
newfieldname)
```

Get External Data File Information

HE5_SWgetextdata

int HE5_SWgetextdata(hid_t *swathID*, char **fieldname*, size_t *namelength*, char **filelist*, off_t *offset[]*, hsize_t *size[]*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
fieldname IN: External field name
namelength OUT: Length of each name entry
filelist OUT: List of file names
offset[] OUT: Array of offsets (in byte) from the beginning of file to the location in file where the data starts
size[] OUT: Array of sizes (in bytes) reserved in the file for the data
Purpose Retrieves information about external data file(s) associated with the data set.
Return value Returns number of external data files if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath ID or field name.

Example In this example, we get information about the *ExtData* field:

```
nfiles = HE5_SWgetextdata(swathID, "ExtData", namlen,  
filenames, offset, size);
```

FORTRAN integer function he5_swgetxdat(*swathid*,*fieldname*,*nlen*,*fllist*,*offset*,*size*)

```
integer      swathid  
integer      nfiles  
integer*4    nlen  
integer*4    offset(*)  
integer*4    size(*)  
character*(*) fieldname  
character*(*) fllist
```

The equivalent *FORTRAN* code for the example above is:

```
nfiles = he5_swgetxdat(swathid, "ExtData",nlen,  
fllist,offset,size)
```

Get Fill Value for a Specified Field

HE5_SWgetfillvalue

herr_t HE5_SWgetfillvalue(hid_t *swathID*, char **fieldname*, void **fillval*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Fieldname

fillval OUT: Space allocated to store the fill value

Purpose Retrieves fill value for the specified field.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.

Description It is assumed the number type of the fill value is the same as the field.

Example In this example, we get the fill value for the *Temperature* field:

```
status = HE5_SWgetfillvalue(swathID, "Temperature",
&tempfill);
```

FORTTRAN integer function he5_swgetfill(*swathid*,*fieldname*,*fillval*)

integer *swathid*

character*(*) *fieldname*

<valid type> *fillval*(*)

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_swgetfill(swathid, "Temperature", tempfill)
```

Retrieve Type of Dimension Mapping when first Dimension is Geodim

HE5_SWgeomapinfo

herr_t HE5_SWgeomapinfo(hid_t *swathID*, char **geodim*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

geodim IN: Dimension name

Purpose Retrieve type of dimension mapping for a dimension.

Return value Returns (2) for indexed mapping, (1) for regular mapping, (0) if dimension is not mapped, or FAIL (-1) otherwise.

Description This routine checks the type of mapping (regular or indexed).

Example In this example, we retrieve information about the type of mapping between the “IdxGeo” and “IdxData” dimensions, defined by *HE5_SWdefidxmap*.

```
status = HE5_SWgeomapinfo(swathID, geodim);
```

We will have regmap = 2 for indexed mapping between the “IdxGeo” and “IdxData” dimensions.

NOTE: If the dimension has regular mapping and indexed, the function will return a value of 3.

FORTTRAN integer function he5_swgmapinfo(*swathid*,*geodim*)

integer *swathid*

character*(*) *geodim*

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_swgmapinfo(swathid, geodim)
```

Return Information about a Group Swath Attribute

HE5_SWgrpattrinfo

herr_t HE5_SWgrpattrinfo(hid_t *swathID*, const char **attrname*, H5T_class_t **ntype*, hsize_t **count*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
attrname IN: Attribute name
numbertype OUT: Data type class ID of attribute
count OUT: Number of attribute elements
Purpose Returns information about a swath group attribute
Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description This routine returns number type and number of elements (count) of a swath group attribute.
Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_SWgrpattrinfo(swathID, "ScalarFloat", &nt,  
&count);
```

The *nt* variable will have the value 1 and *count* will have the value 1.

FORTRAN integer function he5_swgattrinfo(*swathid*, *attrname*, *ntype*, *count*,)
integer *swathid*
character*(*) *attrname*
integer *ntype*
integer *4 *count*

The equivalent *FORTRAN* code for the first example above is:

```
status = he5_swgattrinfo(swathid, "ScalarFloat",nt,count)
```

Retrieve Indexed Geolocation Mapping

HE5_SWidxmapinfo

hsize_t HE5_SWidxmapinfo(hid_t *swathID*, char **geodim*, char **datadim*, long *index*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

geodim IN: Indexed Geolocation dimension name

datadim IN: Indexed Data dimension name

index OUT: Index mapping array

Purpose Retrieve indexed array of specified geolocation mapping.

Return value Returns size of indexed array if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.

Description This routine retrieves the size of the indexed array and the array of indexed elements of the specified geolocation mapping.

Example In this example, we retrieve information about the indexed mapping between the "*IdxGeo*" and "*IdxData*" dimensions:

```
idxsz = HE5_SWidxmapinfo(swathID, "IdxGeo", "IdxData",  
index);
```

The variable, *idxsz*, will be equal to 5 and *index*[5] = {0,2,3,6,7}.

FORTTRAN integer*4 function he5_swimapinfo(*swathid*, *geodim*, *datadim*, *index*)

integer *swathid*

character*(*) *geodim*

character*(*) *datadim*

integer*4 *index*(*)

The equivalent *FORTTRAN* code for the example above is:

```
idxsz = he5_swimapinfo(swathid, "IdxGeo", "IdxData", index)
```

Retrieve Information Swath Attributes

HE5_SWinqattrs

long HE5_SWinqattrs(hid_t *swathID*, char **attrnames*, long **strbufsize*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about attributes defined in swath.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the attributes defined in a swath structure. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_SWinqattrs(swathID, NULL, &strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_SWinqattrs(swathID, attrnames, &strbufsize);
```

The variable, *attrnames*, will be set to:

"*attrOne,attr_2*".

FORTRAN integer*4 function he5_swinqattrs(*swathid*,*attrnames*,*strbufsize*)

integer *swathid*

character*(*) *attrnames*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_swinqattrs(swathid, attrnames, strbufsize)
```

Retrieve Information about Data Fields Defined in Swath

HE5_SWinqdatafields

long HE5_SWinqdatafields(hid_t *swathID*, char **fieldlist*, int *rank*[], H5T_class_t *ntype*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldlist OUT: Listing of data fields (entries separated by commas)

rank OUT: Array containing the rank of each data field

ntype OUT: Array containing the numbertype of each data field

Purpose Retrieve information about all of the data fields defined in swath.

Return value Number of data fields found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.

Description The field list is returned as a string with each data field separated by commas. The *rank* and *ntype* arrays will have an entry for each field. Output parameters set to *NULL* will not be returned.

Example In this example we retrieve information about the data fields:

```
nflds = HE5_SWinqdatafields(swathID, fieldlist, rank,
                             ntype);
```

The parameter, *fieldlist*, will have the value:

"Spectra" with *rank*[1]={3}, *ntype*[1]={1}

FORTTRAN integer*4 function he5_swingdflds(*swathid*, *fieldlist*, *rank*, *ntype*)

integer *swathid*

character*(*) *fieldlist*

integer *rank*(*)

integer *ntype*(*)

The equivalent *FORTTRAN* code for the example above is:

```
nflds = he5_swingdflds(swathid, fieldlist, rank, ntype)
```

Retrieve Information about Dimensions Defined in Swath

HE5_SWinqdims

long HE5_SWinqdims(hid_t *swathID*, char **dimnames*, hsize_t *dims*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

dimnames OUT: Dimension list (entries separated by commas)

dims OUT: Array containing size of each dimension

Purpose Retrieve information about all of the dimensions defined in swath.

Return value Number of dimension entries found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.

Description The dimension list is returned as a string with each dimension name separated by commas. Output parameters set to *NULL* will not be returned.

Example In this example, we retrieve information about the dimensions defined in the *ExampleSwath* structure:

```
ndims = HE5_SWinqdims(swathID, dimnames, dims);
```

The parameter, *dimname*, will have the value:

```
"GeoTrack,GeoXtrack,DataTrack,DataXtrack,Bands,Unlim"
```

```
with ndims = 6, dims[6]={2000,1000,4000,2000,5,0}
```

FORTTRAN integer*4 function he5_swinqdims(*swathid*,*dimnames*,*dims*)

```
integer      swathid
```

```
character*(*) dimnames
```

```
integer*4     dims(*)
```

The equivalent *FORTTRAN* code for the example above is:

```
ndims = he5_swinqdims(swathid, dimnames, dims)
```

Retrieve Information about Geolocation Fields Defined in Swath

HE5_SWinqgeofields

long HE5_SWinqgeofields(hid_t *swathID*, char **fieldlist*, int *rank*[], H5T_class_t *ntype*[])

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
fieldlist OUT: Listing of geolocation fields (entries separated by commas)
rank OUT: Array containing the rank of each geolocation field
ntype OUT: Array containing the numbertype of each geolocation field
Purpose Retrieve information about all of the geolocation fields defined in swath.
Return value Number of geolocation fields found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description The field list is returned as a string with each geolocation field separated by commas. The *rank* and *ntype* arrays will have an entry for each field. Output parameters set to *NULL* will not be returned.

Example In this example, we retrieve information about the geolocation fields:

```
nflds = HE5_SWinqgeofields(swathID, fieldlist, rank,  
                           ntype);
```

The parameter, *fieldlist*, will have the value: "*Longitude,Latitude*" with *nflds* = 2, *rank*[2]={2,2}, *ntype*[2]={1,1}

FORTRAN integer*4 function he5_swinqgflds(swathid, fieldlist, rank, ntype)

integer *swathid*

character*(*) *fieldlist*

integer *rank*(*)

integer *ntype*(*)

The equivalent *FORTRAN* code for the example above is:

```
nflds = he5_swinqgflds(swathid, fieldlist, rank, ntype)
```

Retrieve Information about Swath Group Attributes

HE5_SWinqgrpattrs

long HE5_SWinqgrpattrs(hid_t *swathID*, char **attrnames*, long **strbufsize*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about group attributes defined in swath.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each group attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the group attributes defined for the “Data Fields” group. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_SWinqgrpattrs(swathID, NULL, &strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_SWinqgrpattrs(swathID, attrnames, &strbufsize);
```

The variable, *attrnames*, will be set to:

```
"attrOne,attr_2".
```

FORTRAN integer*4 function he5_swinqgattr(*swathid*, *attrnames*, *strbufsize*)

integer *swathid*

character*(*) *attrnames*

integer*4 *strbufsize*

integer*4 *nattr*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_swinqgattr(swathid, attrnames, strbufsize)
```

Retrieve Information about Indexed Mappings Defined in Swath

HE5_SWinqidxmaps

long HE5_SWinqidxmaps(hid_t *swathID*, char **idxmap*, hsize_t *idxsizes*[])

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>idxmap</i>	OUT: Indexed Dimension mapping list (entries separated by commas)
<i>idxsizes</i>	OUT: Array containing the sizes of the corresponding index arrays.
Purpose	Retrieve information about all of the indexed geolocation/data mappings defined in swath.
Return value	Number of indexed mapping relations found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper Swath ID.
Description	The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/). Output parameters set to <i>NULL</i> , will not be returned.

Example In this example, we retrieve information about the indexed dimension mappings:

```
nidxmaps = HE5_SWinqidxmaps(swathID, idxmap, idxsizes);
```

The variable, *idxmap*, will contain the string:

"*IdxGeo/IdxData*" with *nidxmaps* = 1 and *idxsizes*[1]={5}.

FORTRAN integer*4 function he5_swinqimaps(*swathid*,*dimmap*,*idxsizes*)

integer *swathid*

character*(*) *dimmap*

integer*4 *idxsizes*(*)

The equivalent *FORTRAN* code for the example above is:

```
nidxmaps = he5_swinqimaps(swathid, dimmap, idxsizes)
```

Retrieve Information Swath Local Attributes

HE5_SWinqlocattr

long HE5_SWinqlocattr(hid_t *swathID*, const char **fieldname*, char **attrnames*, long **strbufsize*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Fieldname to retrieve local attribute information

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about local attributes defined for a field.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each local attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the local attributes defined for a field "DataField".. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_SWinqlocattr(swathID, "DataField", NULL,
&strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_SWinqlocattr(swathID, "DataField", attrnames,
&strbufsize);
```

The variable, *attrlist*, will be set to:

"*attrOne,attr_2*".

FORTRAN integer*4 function he5_swinqlattr(*swathid*, *fieldname*, *attrnames*, *strbufsize*)

integer *swathid*

character*(*) *fieldname*

character*(*) *attrnames*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_swinqlattr(swathid, "DataField", attrnames,  
strbufsize)
```

Retrieve Information about Dimension Mappings Defined in Swath

HE5_SWinqmaps

long HE5_SWinqmaps(hid_t *swathID*, char **dimmap*, long *offset*[], long *increment*[])

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>dimmap</i>	OUT: Dimension mapping list (entries separated by commas)
<i>offset</i>	OUT: Array containing the offset of each geolocation relation
<i>increment</i>	OUT: Array containing the increment of each geolocation relation
Purpose	Retrieve information about all of the (non-indexed) geolocation relations defined in swath.
Return value	Number of geolocation relation entries found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper Swath ID.
Description	The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/). Output parameters set to <i>NULL</i> will not be returned.
Example	In this example, we retrieve information about the dimension mappings in the <i>ExampleSwath</i> structure:

```
nmaps = HE5_SWinqmaps(swathID, dimmap, offset, increment);
```

The variable, *dimmap*, will contain the string:
"GeoTrack/DataTrack,GeoXtrack/DataXtrack" with *nmaps* = 2,
offset[2]={0,1} and *increment*[2]={2,2}.

FORTTRAN integer*4 function
he5_swinqmaps(*swathid*,*dimmap*,*offset*,*increment*)
integer *swathid*
character*(*) *dimmap*
integer*4 *offset*(*)
integer*4 *increment*(*)

The equivalent *FORTTRAN* code for the example above is:

```
nmaps = he5_swinqmaps(swathid, dimmap, offset, increment)
```

Retrieve Swath Structures Defined in HDF-EOS File

HE5_SWinqswath

long HE5_SWinqswath(const char * *filename*, char **swathlist*, long **strbufsize*)

filename IN: The HDF-EOS file name

swathlist OUT: Swath list (entries separated by commas)

strbufsize OUT: String length of swath list

Purpose Retrieves number and names of swaths defined in HDF-EOS file.

Return value Number of swaths found if successful or FAIL (-1) otherwise.

Description The swath list is returned as a string with each swath name separated by commas. If *swathlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. If *strbufsize* is also set to NULL, the routine returns just the number of swaths. Note that *strbufsize* does not count the null string terminator.

Example In this example, we retrieve information about the swaths defined in an HDF-EOS file, *Swath.he5*. We assume that there are two swaths stored, *SwathOne* and *Swath_2*:

```
nswath = HE5_SWinqswath("Swath.he5", NULL, &strbufsize);
```

The parameter, *nswath*, will have the value 2 and *strbufsize* will have value 16.

```
nswath = HE5_SWinqswath("Swath.he5", swathlist,  
&strbufsize);
```

The variable, *swathlist*, will be set to:

"SwathOne,Swath_2".

FORTRAN integer*4 function he5_swinqswath(*filename*,*swathlist*,*strbufsize*)

character*(*) *filename*

character*(*) *swathlist*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nswath = he5_swinqswath('Swath.he5', swathlist, strbufsize)
```

Return Information about a Local Swath Attribute

HE5_SWlocattrinfo

herr_t HE5_SWlocattrinfo(hid_t *swathID*, const char **fieldname*, const char **attrname*, H5T_class_t **ntype*, hsize_t **count*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Field name

attrname OUT: Attribute name

ntype OUT: Data type class ID of attribute

count OUT: Number of attribute elements

Purpose Returns information about a Data Field's local attribute(s)

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of a data field's local attribute.

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_SWlocattrinfo(swathID, "DataField", attrname,
&ntype, &count);
```

The *nt* variable will have the value 1 and *count* will have the value 1.

FORTRAN integer function he5_swlattrinfo(*swathid*, *fieldname*, *attrname*, *ntype*,
count)

```
integer      swathid
character*(*) attrname
integer      ntype
integer *4   count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = he5_swlattrinfo(swathid, "DataField", attrname,
ntype, count)
```

Retrieve Offset and Increment of Specific Dimension Mapping

HE5_SWmapinfo

herr_t HE5_SWmapinfo(hid_t *swathID*, char **geodim*, char **datadim*, long **offset*, long **increment*)

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>geodim</i>	IN: Geolocation dimension name
<i>datadim</i>	IN: Data dimension name
<i>offset</i>	OUT: Mapping offset
<i>increment</i>	OUT: Mapping increment
Purpose	Retrieve offset and increment of specific monotonic geolocation mapping.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.
Description	This routine retrieves offset and increment of the specified geolocation mapping.
Example	In this example, we retrieve information about the mapping between the <i>GeoTrack</i> and <i>DataTrack</i> dimensions:

```
status = HE5_SWmapinfo(swathID, "GeoTrack", "DataTrack",  
                        &offset, &increment);
```

The variable *offset* will be 0 and *increment* 2.

FORTRAN integer function he5_swmapinfo(*swathid*, *geodim*, *datadim*, *offset*, *increment*)

```
integer      swathid  
character(*) geodim  
character(*) datadim  
integer*4   offset  
integer*4   increment
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swmapinfo(swathid, "GeoTrack", "DataTrack",  
                        offset, increment)
```

Mount External Data File

HE5_SWmountexternal

hid_t HE5_SWmountexternal(hid_t *swathID*, int *fldgroup*, const char
**extfilename*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fldgroup</i>	IN:	Field group flag
<i>extfilename</i>	IN:	External file name
Purpose		Mount external data file
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This function allows the user to store required data needed by multiple data files into a separate file so it is not repeated throughout the data files.
Example		In this example, we mount a file that contains calibration information needed by the data fields in another file <pre>strcpy(extfilename, "/home/user/data/calibration.hdf5"); fileID = HE5_SWmountexternal(swathID, HE5_HDFE_DATAGROUP, extfilename);</pre>
FORTRAN		Not available with this release.

Return Number of Specified Objects in a Swath

HE5_SWnentries

long HE5_SWnentries(hid_t *swathID*, int *entrycode*, long **strbufsize*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

entrycode IN: Entrycode

strbufsize OUT: String buffer size

Purpose Returns number of entries and descriptive string buffer size for a specified entity.

Return value Number of entries if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id or entry code.

Description This routine can be called before an inquiry routines in order to determine the sizes of the output arrays and descriptive strings. The string length does not include the NULL terminator.

The entry codes are:

HE5_HDFE_NENTDIM (0) - Dimensions

HE5_HDFE_NENTMAP (1) - Dimension Mappings

HE5_HDFE_NENTIMAP (2) - Indexed Dimension Mappings

HE5_HDFE_NENTGFLD (3) - Geolocation Fields

HE5_HDFE_NENTDFLD (4) - Data Fields

Example In this example, we determine the number of dimension mapping entries and the size of the map list string.

```
nmaps = HE5_SWnentries(swathID, HE5_HDFE_NENTMAP, &bufsize);
```

The return value, *nmaps*, will be equal to 2 and *bufsz* = 39

FORTRAN integer*4 function he5_swnentries(*swathid*, *entrycode*, *bufsize*)

integer *swathid*

integer *entrycode*

integer*4 *bufsize*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NENTMAP=1)
```

```
nmaps = he5_swnentries(swathid, HE5_HDFE_NENTMAP, bufsize)
```

Open HDF-EOS File

HE5_SWopen

hid_t HE5_SWopen(const char *filename, uintn access)

filename IN: Complete path and filename for the file to be opened
access IN: H5F_ACC_RDONLY, H5F_ACC_RDWR or H5F_ACC_TRUNC
Purpose Opens or creates HDF-EOS file in order to create, read, or write a Swath.
Return value Returns the swath file id handle (fid) if successful or FAIL (-1) otherwise.
Description This routine creates a new file or opens an existing one, depending on the access parameter.

Access codes:

H5F_ACC_RDONLY Open for read only. If file does not exist, error

H5F_ACC_RDWR Open for read/write. If file does not exist, create it

H5F_ACC_TRUNC If file exist, delete it, then open a new file for read/write

Example In this example, we create a new swath file named, *Swath.he5*. It returns the file handle, *fid*.

```
fid = HE5_SWopen("Swath.he5", H5F_ACC_TRUNC);
```

FORTRAN integer function he5_swopen(filename, access)

character*(*) filename

integer access

The access codes should be defined as parameters:

```
parameter (HE5_HDFE_RDWR = 0)
```

```
parameter (HE5_HDFE_RDONLY = 1)
```

```
parameter (HE5_HDFE_TRUNC = 2)
```

The equivalent FORTRAN code for the example above is:

```
fid = he5_swopen("Swath.he5", HE5_HDFE_TRUNC)
```

Note to users of the SDP Toolkit: Please refer to the *Release 5B SDP Toolkit User Guide for the ECS Project (333-CD-510-001)*, Section 6.2.1.2, for information on how to obtain a file name (referred to as a “physical file handle”) from within a PGE. See also Section 9 of this document for code examples.

Return Information about a Defined Time Period

HE5_SWperiodinfo

herr_t HE5_SWperiodinfo(hid_t *swathID*, hid_t *periodID*, char * *fieldname*,
H5T_class_t **ntype*, int **rank*, hsize_t *dims*[], size_t **size*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

periodID IN: Period ID returned by HE5_SWdeftimeperiod

fieldname IN: Field to subset

ntype OUT: Number type of field

rank OUT: Rank of field

dims OUT: Dimensions of subset period

size OUT: Size in bytes of subset period

Purpose Retrieves information about the subsetted period.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns information about a subsetted time period for a particular field. It is useful when allocating space for a data buffer for the subset. Because of differences in number type and geolocation mapping, a given time period will give different values for the dimensions and size for various fields.

Example In this example, we retrieve information about the time period defined in *HE5_SWdeftimeperiod* for the *Spectra* field. We use this to allocate space for data in the subsetted time period.

```
/* Get size in bytes of time period for "Spectra" field*/
status = HE5_SWperiodinfo(SWid, periodID, "Spectra", &ntype,
                          &rank, dims, &size);

/* Allocate space */
datbuf = (double *)calloc(size, sizeof(double));
```

FORTRAN integer function `he5_swperinfo`(*swathid*, *periodid*, *fieldname*, *ntype*, *rank*,
dims, *size*)

integer	<i>swathid</i>
integer	<i>periodid</i>
character*(*)	<i>fieldname</i>
integer	<i>ntype</i>
integer	<i>rank</i>
integer*4	<i>dims</i> (*)
integer*4	<i>size</i>

The equivalent *FORTRAN* code for the example above is:

```
status=he5_swperinfo(swid,periodid,"Spectra",ntype,rank,dim,  
size)
```

Read Swath Attribute

HE5_SWreadattr

herr_t HE5_SWreadattr(hid_t *swathID*, const char **attrname*, void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "ScalarFloat":

```
status = HE5_SWreadattr(swathID, "ScalarFloat", &data);
```

FORTRAN integer function he5_swrdatr(*swathid*,*attrname*,*datbuf*)

```
integer      swathid
```

```
<valid type> datbuf(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swrdatr(swathid, "ScalarFloat", datbuf)
```

Read External Data Set

HE5_SWreadexternal

herr_t HE5_SWreadexternal(hid_t *swathID*, int *fldgroup*, const char **fieldname*, void **buffer*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fldgroup IN: Field group flag

fieldname IN: Name of field to read

buffer OUT: Output data buffer

Purpose Read external data set

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This function allows the user to get the data required from the external data file.

Example In this example, the field “Cal data” is read from the external file:

```
strcpy(fieldname, "Cal data");  
  
status = HE5_SWreadexternal(swathID, HE5_HDFE_DATAGROUP,  
                             fieldname, buffer);
```

FORTTRAN Not available with this release.

Read Data from a Swath Field

HE5_SWreadfield

herr_t HE5_SWreadfield(hid_t *swathID*, char **fieldname*, const hssize_t *start*[], const hsize_t *stride*[], const hsize_t *edge*[], void **buffer*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Name of field to read

start IN: Array specifying the starting location within each dimension

stride IN: Array specifying the number of values to skip along each dimension

edge IN: Array specifying the number of values to read along each dimension

buffer OUT: Buffer to store the data read from the field

Purpose Reads data from a swath field.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are improper swath id or unknown fieldname.

Description The values within *start*, *stride*, and *edge* arrays refer to the swath field (input) dimensions. The output data in *buffer* is written to contiguously. The default values for *start* and *stride* are 0 and 1 respectively and are used if these parameters are set to *NULL*. The default values for *edge* are $(dim - start) / stride$ where *dim* refers is the size of the dimension.

Example In this example, we read data from the 10th track (0-based) of the *Longitude* field.

```
float    track[1000];  
hssize_t start[2] = {9,1};  
hsize_t  edge[2]  = {1,1000};  
status = HE5_SWreadfield(swathID, "Longitude", start, NULL,  
                        edge, track);
```

FORTRAN integer function `he5_swrdfld(swathid, fieldname, start, stride, edge, buffer)`
 integer *swathid*
 character*(*) *fieldname*
 integer*4 *start*(*)
 integer*4 *stride*(*)
 integer*4 *edge*(*)
 <valid type> *buffer*(*)

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```

real*4    track(1000)
integer*4 start(2), stride(2), edge(2)

start(1) = 0
start(2) = 10
stride(1) = 1
stride(2) = 1
edge(1) = 1000
edge(2) = 1

status=he5_swrdfld(swathid, "Longitude", start, stride,
edge, track)
  
```

Read Group Swath Attribute

HE5_SWreadgrpattr

herr_t HE5_SWreadgrpattr(hid_t *swathID*, const char **attrname*, void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "ScalarFloat":

```
status = HE5_SWreadgrpattr(swathID, "ScalarFloat", &data);
```

FORTRAN integer function he5_swrddgattr(*swathid*,*attrname*,*datbuf*)

```
integer      swathid
```

```
character*(*) attrname
```

```
<valid type> datbuf(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swrddgattr(swathid, "ScalarFloat", datbuf)
```

Read Local Swath Attribute

HE5_SWreadlocattr

herr_t HE5_SWreadlocattr(hid_t *swathID*, const char **fieldname*, const char **attrname*, void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Field name

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = HE5_SWreadlocattr(swathID, "DataField",  
"ScalarFloat", &data);
```

FORTRAN integer function he5_swrldattr(*swathid*, *fieldname*, *attrname*, *datbuf*)

integer *swathid*

character*(*) *fieldname*

character*(*) *attrname*

<valid type> *datbuf*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swrldattr(swathid, "DataField", "ScalarFloat",  
datbuf)
```

Define a Longitude-Latitude Box Region for a Swath

HE5_SWregionindex

hid_t HE5_SWregionindex(hid_t *swathID*, double *cornerlon*[], double *cornerlat*[], int *mode*, char **geodim*, hsize_t *idxrange*[])

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>cornerlon</i>	IN: Longitude in decimal degrees of box corners
<i>cornerlat</i>	IN: Latitude in decimal degrees of box corners
<i>mode</i>	IN: Cross Track inclusion mode
<i>geodim</i>	OUT: Geolocation track dimension
<i>idxrange</i>	OUT: The indices of the region in the geolocation track dimension.
Purpose	Defines a longitude-latitude box region for a swath.
Return value	Returns the swath region ID if successful or FAIL (-1) otherwise.
Description	<p>The difference between this routine and <i>HE5_SWdefbboxregion</i> is the geolocation track dimension name and the range of that dimension are returned in addition to a regionID. Other than that difference they are the same function and this function is used just like <i>HE5_SWdefbboxregion</i>. This routine defines a longitude-latitude box region for a swath. It returns a swath region ID which is used by the <i>HE5_SWextractregion</i> routine to read all the entries of a data field within the region. A cross track is within a region if 1) its midpoint is within the longitude-latitude "box" (HE5_HDFE_MIDPOINT), or 2) either of its endpoints is within the longitude-latitude "box" (HE5_HDFE_ENDPOINT), or 3) any point of the cross track is within the longitude-latitude "box" (HE5_HDFE_ANYPOINT), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the region even though a particular element of the cross track might be outside the region. The swath structure must have both <i>Longitude</i> and <i>Latitude</i> (or <i>Colatitude</i>) fields defined</p>
Example	<p>In this example, we define a region bounded by the 3 degrees longitude, 5 degrees latitude and 7 degrees longitude, 12 degrees latitude. We will consider a cross track to be within the region if its midpoint is within the region.</p> <pre>cornerlon[0] = 3.; cornerlat[0] = 5.;</pre>

```

cornerlon[1] = 7.;
cornerlat[1] = 12.;
regionID = HE5_SWregionindex(swathID, cornerlon, cornerlat,
    HE5_HDFE_MIDPOINT, geodim, idxrange);

```

FORTRAN integer function he5_swregidx(*swathid, cornerlon, cornerlat, mode, geodim, idxrange*)

```

integer      swathid
real*8       cornerlon(*)
real*8       cornerlat(*)
character*(*) geodim
integer*4     idxrange(*)

```

The equivalent *FORTRAN* code for the example above is:

```

parameter (HE5_HDFE_MIDPOINT=0)
cornerlon(1) = 3.
cornerlat(1) = 5.
cornerlon(2) = 7.
cornerlat(2) = 12.
regionid = he5_swregidx(swathid, cornerlon, cornerlat,
    HE5_HDFE_MIDPOINT, geodim, idxrange)

```

Return Information about a Defined Region

HE5_SWregioninfo

herr_t HE5_SWregioninfo(hid_t *swathID*, hid_t *regionID*, char **fieldname*,
H5T_class_t **ntype*, int **rank*, hsize_t *dims*[], size_t **size*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

regionID IN: Region ID returned by HE5_SWdefboxregion

fieldname IN: Field to subset

ntype OUT: Number type of field

rank OUT: Rank of field

dims OUT: Dimensions of subset region

size OUT: Size in bytes of subset region

Purpose Retrieves information about the subsetted region.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns information about a subsetted region for a particular field. It is useful when allocating space for a data buffer for the region. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields.

Example In this example, we retrieve information about the region defined in *HE5_SWdefboxregion* for the *Spectra* field. We use this to allocate space for data in the subsetted region.

```
/* Get size in bytes of region for "Spectra" field*/  
status = HE5_SWregioninfo(SWid, regionID, "Spectra", &ntype,  
                          &rank, dims, &size);  
  
/* Allocate space */  
datbuf = (double *)calloc(size, sizeof(double));
```

FORTRAN integer function `he5_swreginfo(swathid, regionid, fieldname, ntype, rank, dims, size)`

integer	<i>swathid</i>
integer	<i>regionid</i>
character*(*)	<i>fieldname</i>
integer	<i>ntype</i>
integer	<i>rank</i>
integer*4	<i>dims</i> (*)
integer*4	<i>size</i>

The equivalent *FORTRAN* code for the example above is:

```
status =  
he5_swreginfo(swid,regionid, "Spectra", ntype, rank, dims, size)
```

Create an Alias for Swath Data Field

HE5_SWsetalias

herr_t HE5_SWsetalias(hid_t *swathID*, char **fieldname*, const char **aliaslist*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Field name

aliaslist IN: List of alias(es) to associate with the Data Field

Purpose Create an alias for Swath data field

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description Creates aliases that can be used to refer to a Swath data field in addition to the name of the field.

Example In this example, we create an alias for the data field *Temperature*.

```
strcpy(aliaslist, "temps 0 to 30");  
status = HE5_SWsetalias(swathID, "Temperature", aliaslist);
```

FORTRAN integer function he5_swsetalias (*swathid*, *fieldname*, *aliaslist*)
integer *swathid*
character*(*) *fieldname*
character*(*) *aliaslist*

The equivalent *FORTRAN* code for the first example above is:

```
aliaslist = "temps 0 to 30"  
status = he5_swsetalias(swathid, "Temperature", aliaslist)
```

Set External Data File(s)

HE5_SWsetextdata

herr_t HE5_SWsetextdata(hid_t *swathID*, const char **filelist*, off_t *offset[]*,
hsize_t *size[]*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
filelist IN: List of external file names
offset[] IN: Array of offsets (in byte) from the beginning of file to the location
in file where the data starts
size[] IN: Array of sizes (in bytes) reserved in the file for the data

Purpose Sets the external data file(s) associated with the data set.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical
reasons for failure are an improper swath ID.

Example In this example, we set the *ExtData* field:

```
status = HE5_SWsetextdata(swathID, "ext-1.dat,ext-2.dat,ext-  
3.dat", offset, size);
```

FORTRAN integer function he5_swsetxdat(*swathid*,*flist*,*offset*, *size*)

integer *swathid*

integer *status*

integer*4 *offset*(*)

integer*4 *size*(*)

character*(*) *flist*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swsetxdat(swathid,flist,offset,size)
```

Set Fill Value for a Specified Field

HE5_SWsetfillvalue

herr_t HE5_SWsetfillvalue(hid_t *swathID*, char **fieldname*, hid_t *ntype*, void **fillvalue*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
fieldname IN: Field name
ntype IN: Number type of fill value (should match the number type of a specified field)
fillvalue IN: Pointer to the fill value to be used

Purpose Sets fill value for the specified field.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.

Description The fill value is placed in all elements of the field which have not been explicitly defined. The field must have 2 or more dimensions.

Example In this example, we set a fill value for the *Temperature* field:

```
tempfill = -999.0;  
status = HE5_SWsetfillvalue(swathID, "Temperature", ntype,  
&tempfill);
```

FORTRAN integer function he5_swsetfill(*swathid*, *fieldname*, *ntype*, *fillvalue*)

```
integer      swathid  
character*(*) fieldname  
integer      ntype  
<valid type> fillvalue(*)
```

The equivalent *FORTRAN* code for the example above is:

```
fillvalue = -999.0  
status = he5_swsetfill(swathid, "Temperature", ntype,  
fillvalue)
```

Dismount External Data File

HE5_SWunmount

herr_t HE5_SWunmount(hid_t *swathID*, int *fldgroup*, hid_t *fileID*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>fldgroup</i>	IN:	Field group flag
<i>fileID</i>	IN:	ID of file returned by HE5_SWmountexternal
Purpose		Dismount external data file
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This function dismounts from the external file once the user has completed using the data in the file.
Example		In this example, we dismount from the file used in the previous function <pre>status = HE5_SWunmount(swathID, HE5_HDFE_DATAGROUP, fileID);</pre>
FORTRAN		Not available with this release.

Update map index for a specified region

HE5_SWupdateidxmap

long HE5_SWupdateidxmap(int *swathID*, hid_t *regionID*, long *indexin*[], long *indexout*[], long *indices*[])

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or Swattach.
<i>regionID</i>	IN: Region ID returned by HE5_SWdefboxregion.
<i>indexin</i>	IN: The array containing the indices of the data dimension to which each geolocation element corresponds.
<i>indexout</i>	OUT: The array containing the indices of the data dimension to which each geolocation corresponds in the subsetted region. The indexout set to NULL, will not be returned.
<i>indices</i>	OUT: The array containing the indices for start and stop of region.
Purpose	Retrieve indexed array of specified geolocation mapping for a specified region.
Return value	Returns size of updated indexed array if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.
Description	This routine retrieves the size of the indexed array and the array of indexed elements of the specified geolocation mapping for the specified region.
Example	In this example, we retrieve information about the indexed mapping between the “IdxGeo” and “IdxData” dimensions, defined by <i>HE5_SWdefboxregion</i> :

```
/* Get size of index_region array */
idxsz = HE5_SWupdateidxmap(swathID, regionID, index, NULL,
indices);

/* Allocate memory for index_region */
index_region = (long)malloc(sizeof(long) * idxsz);

/* Get the array index_region */
idxsz = HE5_SWupdateidxmap(swathID, regionID, index,
index_region, indices);
```

FORTRAN integer*4 function he5_swupimap(*swathid, regionid, indexin, indexout, indices*)

integer *swathid*

integer *regionid*

integer*4 *indexin*(*)

integer*4 *indexout*(*)

integer*4 *indices*(2)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_swupdateidxmap(swathid, regionid, index, index_region, indices)
```

Write/Update Swath Attribute

HE5_SWwriteattr

herr_t HE5_SWwriteattr(hid_t *swathID*, const char **attrname*, hid_t *ntype*,
hsize_t *count*[], void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrname IN: Attribute name

ntype IN: Number type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates attribute in a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.

Example In this example, we write a floating point number with the name "ScalarFloat" and the value 3.14:

```
attr_val = 3.14;  
  
status = HE5_SWwriteattr(swathid, "ScalarFloat",  
H5T_NATIVE_FLOAT, 1, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;  
  
status = HE5_SWwriteattr(swathid, "ScalarFloat",  
H5T_NATIVE_FLOAT, 1, &attr_val);
```

FORTRAN integer function `he5_swwrattr(swathid, attrname, ntype, count, datbuf)`
integer *swathid*
character*(*) *attrname*
integer*4 *count*(*)
<valid type> *datbuf*(*)

The equivalent *FORTRAN* code for the first example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT = 1)
datbuf = 3.14
count = 1
status = he5_swwrattr(swathid, "ScalarFloat",
HE5_HDFE_NATIVE_FLOAT, count, datbuf)
```

Write Field Metadata for an Existing Swath Data Field

HE5_SWwritedatameta

herr_t HE5_SWwritedatameta(hid_t *swathID*, const char **fieldname*, char **dimlist*, int *mvalue*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Name of field

dimlist IN: The list of data dimensions defining the field

mvalue IN: The number type of the data stored in the field

Purpose Writes field metadata for an existing swath data field.

Return value Returns SUCCEEDED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.

Description This routine writes field metadata for an existing data field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the *HE5_SWdefdim* routine before this routine is called.

Example In this example we write the metadata for the “Band_1” data field used in the swath.

```
status = HE5_SWwritedatameta(swathID, "Band_1", "GeoTrack,  
GeoXtrack", H5T_NATIVE_FLOAT);
```

FORTRAN integer function

```
he5_swrdmeta(swathid,fieldname,dimlist,mvalue)
```

```
integer swathid
```

```
character*(*) fieldname
```

```
character*(*) dimlist
```

```
integer mvalue
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT = 1)
```

```
status = he5_swrdmeta(swathID, "Band_1", "GeoXtrack,  
GeoTrack", HE5_HDFE_NATIVE_FLOAT)
```

The dimensions are entered in *FORTRAN* order with the first dimension being incremented first.

Write Data to a Swath Field

HE5_SWwritefield

herr_t HE5_SWwritefield(hid_t *swathID*, char **fieldname*, const hssize_t *start*[], const hsize_t *stride*[], const hsize_t *edge*[], void **data*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
fieldname IN: Name of field to write
start IN: Array specifying the starting location within each dimension (0-based)
stride IN: Array specifying the number of values to skip along each dimension
edge IN: Array specifying the number of values to write along each dimension
data IN: Values to be written to the field

Purpose Writes data to a swath field.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or unknown fieldname.

Description The values within *start*, *stride*, and *edge* arrays refer to the swath field (output) dimensions. The input data in the *data* buffer is read from contiguously. The default values for *start* and *stride* are 0 and 1 respectively and are used if these parameters are set to *NULL*. The default values for *edge* are $(dim - start) / stride$ where *dim* refers is the size of the dimension. It is the users responsibility to make sure the data buffer contains sufficient entries to write to the field. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines.

Example In this example, we write data to the *Longitude* field.

```
float longitude [2000][1000];  
  
/* Define elements of longitude array */  
  
status = HE5_SWwritefield(swathID, "Longitude", NULL, NULL,  
                          NULL, longitude);
```

We now update Track 10 (0 - based) in this field:

```
float newtrack[1000];  
hssize_t start[2]={10,0}; hsize_t edge[2]={1,1000};  
/* Define elements of newtrack array */  
status = HE5_SWwritefield(swathID, "Longitude", start, NULL,  
edge, newtrack);
```

FORTTRAN

integer function

he5_swwrflld(*swathid,fieldname,start,stride,edge,data*)

integer *swathid*

character*(*) *fieldname*

integer*4 *start*(*)

integer*4 *stride*(*)

integer*4 *edge*(*)

<valid type> *data*(*)

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTTRAN* code for the example above is:

```
real*4 longitude(1000,2000)  
integer*4 start(2), stride(2), edge(2)  
start(1) = 0  
start(2) = 10  
stride(1) = 1  
stride(2) = 1  
edge(1) = 1000  
edge(2) = 2000  
status = he5_swwrflld(swathid, "Longitude", start, stride,  
edge, longitude)
```

We now update Track 10 (0 - based) in this field:

```
real*4 newtrack(1000)  
integer*4 start(2), stride(2), edge(2)
```

```
start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 1000
edge(2) = 1
status = he5_swwrfld(swathid, "Longitude", start, stride,
edge, newtrack)
```

Write Field Metadata to an Existing Swath Geolocation Field

HE5_SWwritegeometa

herr_t HE5_SWwritegeometa(hid_t *swathID*, const char **fieldname*, char **dimlist*, int *mvalue*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Name of field

dimlist IN: The list of geolocation dimensions defining the field

mvalue IN: The number type of the data stored in the field

Purpose Writes field metadata for an existing swath geolocation field.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.

Description This routine writes field metadata for an existing geolocation field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the *HE5_SWdefdim* routine before this routine is called.

Example In this example we write the metadata for the *Latitude* geolocation field used in the swath.

```
status = HE5_SWwritegeometa(swathID, "Latitude",  
                             "GeoTrack,GeoXtrack", H5T_NATIVE_FLOAT);
```

FORTRAN integer function

```
he5_swwrgmeta(swathid,fieldname,dimlist,mvalue)
```

```
integer      swathid
```

```
character*(*) fieldname
```

```
character*(*) dimlist
```

```
integer      mvalue
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT = 1)
```

```
status = he5_swrgmeta(swathID, "Latitude",  
                      "GeoXtrack,GeoTrack",HE5_HDFE_NATIVE_FLOAT)
```

The dimensions are entered in *FORTRAN* order with the first dimension being incremented first.

Write/Update Group Swath Attribute

HE5_SWwritegrpattr

herr_t HE5_SWwritegrpattr(hid_t *swathID*, const char **attrname*, hid_t *ntype*,
hsized_t *count*[], void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

attrname IN: Attribute name

ntype IN: Data type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates group attribute in a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call. The attribute is linked to the "Data Fields" group in the swath file.

Example In this example, we write a single precision (32 bit) floating point number with the name "ScalarFloat" and the value 3.14:

```
count[0] = 1;  
  
attr_val = 3.14;  
  
status = HE5_SWwritegrpattr(swathid, "ScalarFloat",  
H5T_NATIVE_FLOAT, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;  
  
status = HE5_SWwritegrpattr(swathid, "ScalarFloat",  
H5T_NATIVE_FLOAT, count, &attr_val);
```

FORTRAN integer function `he5_swwrgattr(swathid, attrname, ntype, count, datbuf)`
integer *swathid*
character*(*) *attrname*
integer *ntype*
integer*4 *count*(*)
<valid type> *datbuf*(*)

The equivalent *FORTRAN* code for the first example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
datbuf = 3.14
count = 1
status = he5_swwrgattr(swathid, "ScalarFloat",
HE5_HDFE_NATIVE_FLOAT, count, datbuf)
```

Write/Update Local Swath Attribute

HE5_SWwritelocatrr

herr_t HE5_SWwritelocatrr(hid_t *swathID*, const char **fieldname*, char **attrname*, hid_t *ntype*, hsize_t *count*[], void **datbuf*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

fieldname IN: Field name

attrname IN: Attribute name

ntype IN: Data type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates group attribute in a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call. The attribute is linked to a particular "Data Field" in the swath file.

Example In this example, we write a floating point number with the name "ScalarFloat" and the value 3.14:

```
countt[0] = 1;
attr_val = 3.14;
status = HE5_SWwritelocatrr(swathid, "DataField",
"ScalarFloat", H5T_NATIVE_FLOAT, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;
status = HE5_SWwritelocatrr(swathid, "DataField",
"ScalarFloat", H5T_NATIVE_FLOAT, count, &attr_val);
```

FORTTRAN integer function `he5_swrlattr(swathid, fieldname, attrname, ntype, count, datbuf)`

integer *swathid*

character*(*) *fieldname*

character*(*) *attrname*

integer *ntype*

integer*4 *count*(*)

<valid type> *datbuf*(*)

The equivalent *FORTTRAN* code for the first example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
datbuf = 3.14
count = 1
status = he5_swrlattr(swathid, "DataField", "ScalarFloat",
HE5_HDFE_NATIVE_FLOAT,count, datbuf)
```

Define Profile Data Structure

HE5_PRdefine

herr_t HE5_PRdefine(hid_t *swathID*, const char **profilename*, char **dimlist*, char **maxdimlist*, hid_t *datatype_id*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>profilename</i>	IN:	Profile name
<i>dimlist</i>	IN:	List of profile dimensions (separated by comma)
<i>maxdimlist</i>	IN:	List of profile maximum dimensions (separated by comma)
<i>dtype</i>	IN:	Base data type ID
Purpose		Sets up a specified profile structure in a swath.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath ID or data type ID.
Description		The profile is linked to the “Data Fields” group in the swath file.
Example		In this example, we define a profile with the name <i>SimpleProfile</i> and with the base ‘unsigned int’ data type. The profile is represented by a single dataset with 4 dimensions.

```
status = HE5_PRdefine(swathid, "SimpleProfile", dimlist,
maxdimlist, H5T_NATIVE_UINT);
```

FORTRAN integer function he5_prdefine(*swathid*, *profilename*, *rank*, *dim*, *datatype_id*)

```
integer      swathid
character(*) profilename
character(*) dimlist
character(*) maxdimlist(*)
integer      datatype_id
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_INT = 0)
status = he5_prdefine(swathid, "SimpleProfile", dimlist, maxdimlist,
HE5_HDFE_NATIVE_INT)
```

Return Information about a Profile in a Swath

HE5_PRinfo

herr_t HE5_PRinfo(hid_t *swathID*, const char **profname*, int **rank*, hsize_t *dims*[], hsize_t *maxdims*[], H5T_class_t **classID*, char **dimlist*, char **maxdimlist*)

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>profname</i>	IN: Profile name
<i>rank</i>	OUT: Rank of profile dataset
<i>dims</i>	OUT: Array of dimension sizes
<i>maxdims</i>	OUT: Array of maximum dimension sizes
<i>classID</i>	OUT: Base-data type class ID
<i>dimlist</i>	OUT: Comma separated list of dimension names
<i>maxdimlist</i>	OUT: Comma separated list of maximum dimension names
Purpose	Retrieve information about specified profile dataset in a Swath
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine returns rank, array of dimension and maximum dimension sizes, base data type class ID, comma separated list of dimension and maximum dimension names of profile dataset.
Example	In this example, we retrieve information about profile "Profile-2000": <pre>status = HE5_PRinfo(swathID,"Profile-2000", rank, dims, maxdims, classID, dimlist, maxdimlist);</pre>

FORTTRAN integer function he5_prinfo(*swathid*, *profname*, *rank*, *dims*, *maxdims*,
classid, *dimlist*, *maxdimlist*)
integer *swathid*
character*(*) *profname*
integer *rank*
integer*4 *dims*(*)
integer*4 *maxdims*(*)
integer *classID*
character*(*) *dimlist*

character*(*) *maxdimlist*

The equivalent *FORTRAN* code for the first example above is:

```
profname = "Profile-2000"
```

```
status = he5_prinfo(swathid, profname, rank, dims, maxdims,  
classid, dimlist, maxdimlist)
```

Retrieve Information about Profiles in a Swath

HE5_PRInquire

long HE5_PRInquire(hid_t *swathID*, char **profnames*, int **rank*, H5T_class_t **classID*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
profnames OUT: Buffer for returned comma separated list of profile names
rank OUT: Array of ranks of profile datasets
classID OUT: Array of base-data type class IDs of profiles
Purpose Retrieve information about profile datasets in a specified Swath
Return value Returns number of profiles if successful or FAIL (-1) otherwise.
Description A comma separated list of profile datasets is returned. The *rank* and (base data type) *classID* arrays will have an entry for each profile.
Example In this example, we retrieve information about profiles:

```
nprof = HE5_PRInquire(swathID, profnames, rank, classID);
```

FORTTRAN integer*4 function he5_prinquire (*swathid*, *profnames*, *rank*, *classID*)
integer *swathid*
character*(*) *profnames*
integer *rank*(*)
integer *classID*(*)

The equivalent *FORTTRAN* code for the first example above is:

```
nprof = he5_prinquire(swathid, profnames, rank, classID)
```

Read Data from Profile Structure

HE5_PRread

herr_t HE5_PRread(hid_t *swathID*, const char **profilename*, const hssize_t *start*[], const hsize_t *stride*[], const hsize_t *edge*[], void **datbuf*)

<i>swathID</i>	IN: Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>profilename</i>	IN: Profile structure name
<i>start</i>	IN: Array specifying starting location within each dimension
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to write along each dimension
<i>datbuf</i>	OUT: Buffer allocated to hold profile values
Purpose	Reads profile data set from a swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or incorrect profile name.
Description	After reading the data a call to <i>HE5_PRreclaimspace()</i> should be made to release allocated memory.
Example	In this example, we read an ‘unsigned int’ type profile with the name "SimpleProfile":

```
/* Native HDF5 Datatype used in this example: Variable
Length Datatype struct */
typedef struct {
    size_t len; /* Length of VL data (for base type)*/
    void *p; /* Pointer to VL data */
} hvl_t;

hvl_t buffer[4];
start[0] = 0;
```

```

stride[0] = 1;
edge[0]    = 4;

status = HE5_PRread(swathID, "SimpleProfile", start, stride,
edge, buffer);

for (i=0; i<4; i++){
printf("The length of %d-th element is %d \n",
i,(unsigned)buffer[i].len);

    for (j=0; j<2; j++)

        printf("%d \n", ((unsigned int*)buffer[i].p)[j]);
}

status = HE5_PRreclaimspace(swathID, "SimpleProfile",
buffer);

```

FORTRAN integer function
 he5_prread(*swathid, profname, start, stride, count, len, buffer*)

 integer *swathid, status*

 character **(*) profname*

 integer*4 *start(2), stride(2), count(2), len(4)*

The equivalent *FORTRAN* code for the example above is:

```

start(1) = 0
stride(1) = 1
count(1) = 4

status = he5_prread(swathid, "SimpleProfile", start, stride,
count, len, buffer)

```

Reclaim Memory used by “Read” Buffer

HE5_PRreclaimspace

herr_t HE5_PRreclaimspace(hid_t *swathID*, const char **profilename*, void **buffer*)

swathID IN: Swath ID returned by HE5_SWcreate or HE5_SWattach

profilename IN: Profile name

buffer IN: Data buffer used to read profile dataset

Purpose Release memory used by the buffer in the call HE5_PRread()

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description Reclaims memory space allocated to the data buffer in the call *HE5_PRread()*.

Example In this example, we reclaim memory allocated for the “read” buffer “buffer”

```
status = HE5_PRreclaimspace(swathID, "Profile-2000",  
buffer);
```

FORTTRAN Not needed.

Write Data to the Profile Swath Structure

HE5_PRwrite

herr_t HE5_PRwrite(int *swathID*, const char **profilename*, const hssize_t *start*[], const hsize_t *stride*[], const hsize_t *edge*[], size_t *size*, void **datbuf*)

<i>swathID</i>	IN:	Swath ID returned by HE5_SWcreate or HE5_SWattach
<i>profilename</i>	IN:	Profile structure name
<i>start</i>	IN:	Array specifying the starting location within each dimension (0-based)
<i>stride</i>	IN:	Array specifying the number of values to skip along each dimension
<i>edge</i>	IN:	Array specifying the number of values to write along each dimension
<i>size</i>	IN:	Size of data buffer (in bytes) for memory allocation routine
<i>datbuf</i>	IN:	Profile data values

Purpose Writes profile data set in a swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or profile name.

Description The specified profile is linked to a "Data Fields" group in the swath file.

Example In this example, we write data to "SimpleProfile" :

```
size_t      datasize = 0;
hvl_t      buf[4];
for (i = 0; i < 4; i++){
    buf[i].p = malloc(25*(i+1)*sizeof(unsigned int));
    buf[i].len = 25*(i+1);
    datasize += buf[i].len *sizeof(unsigned int);
    for (j = 0; j < 25*(i+1); j++)
        ((unsigned int )buf[i].p)[j] = (i+1)*10+j;
}
```

```
status = HE5_PRwrite(swathid, "SimpleProfile", start,  
stride, edge, datasize, buf);
```

FORTTRAN integer function he5_prwrite(*swathid, profname, start, stride, count,*
datasize, len, buffer)

integer *swathid, status*

integer*4 *start(3), stride(3), count(3), len(4), datasize*

integer *buffer(*), i, j, counter*

The equivalent *FORTTRAN* code for the example above is:

```
datasize = 0
```

```
counter = 0
```

```
do i=1,4
```

```
    len(i) = i*25
```

```
    datasize = datasize + len(i)
```

```
    do j = 1, (25*i)
```

```
        counter = counter + 1
```

```
        buffer(counter) = (i)*1000+j-1
```

```
    enddo
```

```
enddo
```

```
start(1) = 0
```

```
stride(1) = 1
```

```
count(1) = 4
```

```
status = he5_prwrite(swathid, "SimplePrifile", start,  
stride, count, datasize, len, buffer)
```

2.1.3 Grid Interface Functions

This section contains an alphabetical listing of all the functions in the Grid interface. The functions are alphabetized based on their C-language names.

Attach to an Existing Grid Structure

HE5_GDattach

hid_t HE5_GDattach(hid_t *fid*, char **gridname*)

fid IN: Grid file ID returned by HE5_GDopen

gridname IN: Name of grid to be attached

Purpose Attaches to an existing grid within the file.

Return value Returns the grid handle(gridID) if successful or FAIL(-1) otherwise. Typical reasons for failure are improper grid file id or grid name.

Description This routine attaches to the grid using the *gridname* parameter as the identifier.

Example In this example, we attach to the previously created grid, "*ExampleGrid*", within the HDF-EOS file, *Grid.he5*, referred to by the handle, *fid*:

```
gridID = HE5_GDattach(fid, "ExampleGrid");
```

The grid can then be referenced by subsequent routines using the handle, *gridID*.

FORTRAN integer function he5_gdattach(*fid*, *gridname*)

integer *fid*

character*(*) *gridname*

The equivalent *FORTRAN* code for the example above is:

```
gridid = he5_gdattach(fid, "ExampleGrid")
```

Return Information about a Grid Attribute

HE5_GDattrinfo

herr_t HE5_GDattrinfo(hid_t *gridID*, const char **attrname*, H5T_class_t * *ntype*, hsize_t **count*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

ntype OUT: Number type of attribute

count OUT: Number of total bytes in attribute

Purpose Returns information about a grid attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (*count*) of a grid attribute.

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_GDattrinfo(gridID, "ScalarFloat", &ntype, &count);
```

The *ntype* variable will have the value 5 and *count* will have the value 4.

FORTTRAN integer function he5_gdattrinfo(*gridid*, *attrname*, *ntype*, *count*,)

integer *gridid*

character*(*) *attrname*

integer *ntype*

integer*4 *count*

The equivalent *FORTTRAN* code for the first example above is:

```
status = he5_gdattrinfo(gridid, "ScalarFloat", ntype, count)
```

Write Block SOM Offset

HE5_GDbkSOMoffset

herr_t HE5_GDbkSOMoffset(hid_t *gridID*, long *offset[]*, hsize_t *count*, char **code*)

<i>gridID</i>	IN: Grid ID returned by HE5_GDcreate or HE5_GDattach
<i>offset</i>	IN: Offset values for SOM Projection data
<i>count</i>	IN: Number of offset values to write
<i>code</i>	IN: Write/Read code
Purpose	Write block SOM offset values.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	The routine supports structures that contain data which have been written in the Solar Oblique Mercator (SOM) projection. The structure can contain one to many blocks, each with corner points defined by latitude and longitude. The routine can only be used by grids that use the SOM projection. The routine writes the offset values, in pixels, from a standard SOM projection. There is an offset value for every block in the grid except for the first block. The count parameter is used as a check for the number of offset values. This routine will also return the offset values, but the user must know how large the offset array needs to be before calling the function, in that case the code value would be "r" and the count parameter has to be provided also.
Example	<p>In this example, we first show how the SOM projection is defined using HE5_GDdefproj, then we show how the SOM projection is modified using HE5_GDbkSOMoffset:</p> <p>The first parameter is the Grid ID, the second is the projection code for the SOM projection, the third is the zone code, not needed for the SOM projection, the fourth is the sphere code, not needed for the SOM projection and the last parameter is the projection parameter array. Each projection supported by the Grid interface has a unique set of variables that are used by the GCTP library and they are passed to the GCTP library through this array. As you can see below, the twelfth parameter is set to a non-zero value, it is set to the size of the number of blocks in the data field. This is required if the function HE5_GDbkSOMoffset is going to be called. The GCTP library doesn't use this parameter for the SOM projection so that is used by the HDF-EOS library only. The</p>

HE5_GDbkSOMoffset function checks that parameter first before anything else is done.

```
projparm[0] = 6378137.0;
projparm[1] = 0.006694348;
projparm[3] = HE5_EHconvAng(98.161, HE5_HDFE_DEG_DMS);
projparm[4] =
HE5_EHconvAng(87.11516945924, HE5_HDFE_DEG_DMS);
projparm[8] = 0.068585416 * 1440;
projparm[9] = 0.0;
projparm[11] = 6;
status = HE5_GDdefproj(GDdid_som, HE5_GCTP_SOM, NULL, NULL,
projparm);
```

Now that the projection has been defined, HE5_GDbkSOMoffset can be called:

```
offset[5] = {5, 10, 12, 8, 2};
count = 5;
code = "w";
status = HE5_GDbkSOMoffset(gridID, offset, count, code);
```

This set the offset for the second block to 5 pixels, the third block to 10 pixels, fourth block to 12 pixels, fifth to 8 pixels and the sixth block to 2 pixels.

NOTE: This routine is currently implemented in "C" only. If the need arises, a FORTRAN function will be added.

Interblock subsetting is not currently supported by the ECS Science Data Server, at this time. That is, a response to a request to return data contained within a specified latitude/longitude box, will be in an integral number of blocks.

Related Documents

An Album of Map Projections, USGS Professional Paper 1453, Snyder and Voxland, 1989

Map Projections - A Working Manual, USGS Professional Paper 1395, Snyder, 1987

Close an HDF-EOS File

HE5_GDclose

herr_t HE5_GDclose(hid_t *fid*)

fid IN: Grid file ID returned by HE5_GDopen

Purpose Closes file.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine closes the HDF-EOS grid file.

Example

```
status = HE5_GDclose(fid);
```

FORTRAN integer function he5_gdclose(*fid*)

integer *fid*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdclose(fid)
```

Retreive Compression Information for Field

HE5_GDcompinfo

herr_t HE5_GDcompinfo(hid_t *gridID*, const char **fieldname*, char **compcode*,
int *compparm*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Fieldname

compcode OUT: HDF compression code

compparm OUT: Compression parameters

Purpose Retrieves compression information about a field.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine returns the compression code and compression parameters for a given field.

Example To retrieve the compression information about the *Opacity* field defined in the *HE5_GDdefcomp* section:

```
status = HE5_GDcompinfo(gridID, "Opacity", compcode,  
compparm);
```

The *compcode* parameter will be set to 4 and *compparm*[0] to 5.

FORTRAN integer function he5_gdcompinfo(*gridid*,*fieldname* *compcode*, *compparm*)

integer *gridid*

character*(*) *fieldname*

character*(*) *compcode*

integer *compparm*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdcompinfo(gridid, 'Opacity', compcode,  
compparm)
```

The *compcode* parameter will be set to 4 and *compparm*(1) to 5.

Create a New Grid Structure

HE5_GDcreate

hid_t HE5_GDcreate(hid_t *fid*, const char **gridname*, long *xdimsize*, long *ydimsize*, double *upleftpt*[], double *lowrightpt*[])

fid IN: Grid file ID returned by HE5_GDopen
gridname IN: Name of grid to be created
xdimsize IN: Number of columns in grid
ydimsize IN: Number of rows in grid
upleftpt IN: Location, of upper left corner of the upper left pixel
lowrightpt IN: Location, of lower right corner of the lower right pixel

Purpose Creates a grid within the file.

Return value Returns the grid handle(*gridID*) or FAIL(-1) otherwise.

Description The grid is created as a group within the HDF-EOS file with the name *gridname*. This routine establishes the resolution of the grid, ie, the number of rows and columns, and it's location within the complete global projection through the *upleftpt* and *lowrightpt* arrays. These arrays should be in meters for all GCTP projections other than the Geographic Projection, which should be in packed degree format. q.v. below.

Example In this example, we create a UTM grid bounded by 54 E to 60 E longitude and 20 N to 30 N latitude. We divide it into 120 bins along the x-axis and 200 bins along the y-axis

```
upleft[0]=210584.50041;  
upleft[1]=3322395.95445;  
lowrgt[0]=813931.10959;  
lowrgt[1]=2214162.53278;  
xdim=120;  
ydim=200;  
gridID = HE5_GDcreate(fid, "UTMGrid", xdim, ydim, uplft,  
lowrgt);
```

The grid structure is then referenced by subsequent routines using the handle, *gridID*.

The *xdim* and *ydim* values are referenced in the field definition routines by the reserved dimensions: *XDim* and *YDim*.

For the Polar Stereographic, Goode Homolosine and Lambert Azimuthal projections, we have established default values in the case of an entire hemisphere for the first projection, the entire globe for the second and the entire polar or equatorial projection for the third. Thus, if we have a Polar Stereographic projection of the Northern Hemisphere then the *uplft* and *lowrgt* arrays can be replaced by *NULL* in the function call.

In the case of the Geographic projection (linear scale in both longitude latitude), the *upleftpt* and *lowrightpt* arrays contain the longitude and latitude of these points in packed degree format (DDDMMMSSS.SS).

Note:

upleftpt - Array that contains the X-Y coordinates of the upper left corner of the upper left pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The upper left X coordinate value should be the lowest X value of the grid. The upper left Y coordinate value should be the highest Y value of the grid.

lowrightpt - Array that contains the X-Y coordinates of the lower right corner of the lower right pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The lower right X coordinate value should be the highest X value of the grid. The lower right Y coordinate value should be the lowest Y value of the grid.

If the projection id geographic (i.e., projcode=0) then the X-Y coordinates should be specified in degrees/minutes/seconds (DDDMMMSSS.SS) format. The first element of the array holds the longitude and the second element holds the latitude. Latitudes are from -90 to +90 and longitudes are from -180 to +180 (west is negative).

For all other projection types the X-Y coordinates should be in *meters* in double precision. These coordinates have to be computed using the GCTP software with the same projection parameters that have been specified in the **projparm** array. For UTM projections use the same zone code and its sign (positive or negative) while computing both upper left and lower right corner X-Y coordinates irrespective of the hemisphere.

To convert lat/long to x-y coordinates, it is also possible to use SDP Toolkit routines: *PGS_GCT_Init()* or *PGS_GCT_Proj()*. More information is contained in the *SDP Toolkit Users Guide for the ECS Project*

FORTRAN integer function *he5_gdcreate(fid, gridname, xdimsize, ydimsize, upleftpt, lowrightpt)*

integer *fid*

character*(*) *gridname*

integer*4 *xdimsize*

integer*4 *ydimsize*

real*8 *upleftpt(2)*

real*8 *lowrightpt(2)*

The equivalent *FORTRAN* code for the example above is:

```
gridid = he5_gdcreate(fid, "UTMGrid", xdim, ydim, uplft,  
                    lowrgt)
```

The default values for the Polar Stereographic and Goode Homolosine can be designated by setting all elements in the *uplft* and *lowrgt* arrays to 0.

Define Region of interest by Latitude/Longitude

HE5_GDdefboxregion

hid_t HE5_GDdefboxregion(hid_t *gridID*, double *cornerlon*[], double *cornerlat*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

cornerlon IN: Longitude in decimal degrees of box corners

cornerlat IN: Latitude in decimal degrees of box corners

Purpose Defines a longitude-latitude box region for a grid.

Return value Returns the grid region ID if successful or FAIL (-1) otherwise.

Description This routine defines a longitude-latitude box region for a grid. It returns a grid region ID which is used by the *HE5_GDextractregion* routine to read all the entries of a data field within the region.

Example In this example, we define the region to be the first quadrant of the Northern hemisphere.

```
cornerlon[0] = 0.;    cornerlat[0] = 90.;  
cornerlon[1] = 90.;  cornerlat[1] = 0.;  
regionID = HE5_GDdefboxregion(GDdid, cornerlon, cornerlat);
```

FORTRAN integer function he5_gddefboxreg(*gridid*, *cornerlon*, *cornerlat*)

```
integer  gridid  
real*8  cornerlon(2)  
real*8  cornerlat(2)
```

The equivalent *FORTRAN* code for the example above is:

```
cornerlon(1) = 0.  
cornerlat(1) = 90.  
cornerlon(2) = 90.  
cornerlat(2) = 0.  
regionid = he5_gddefboxreg(gridid, cornerlon,cornerlat)
```

Set Grid Field Compression

HE5_GDdefcomp

herr_t HE5_GDdefcomp(hid_t *gridID*, int *compcode*, int *compparm*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

compcode IN: HDF compression code

compparm IN: Compression parameters (if applicable)

Note: Only deflate compression is supported in this release.

Purpose Sets the field compression for all subsequent field definitions.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine sets the HDF field compression for subsequent grid field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported are: run length encoding (HE5_COMP_DEFLATE=4) and no compression (HE5_COMP_NONE = 0, the default). Deflate compression requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression. Compressed fields are written using the standard *HE5_GDwritefield* routine, however, the entire field must be written in a single call. If this is not possible, the user should consider tiling. See *HE5_GDdeftile* for further information. Any portion of a compressed field can then be accessed with the *HE5_GDreadfield* routine. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of the compression schemes and parameters.

Example Suppose we wish to compress the fields *Pressure*, *Opacity* and *Spectra* using deflate compression, and use no compression for the *Temperature* field.

```
status = HE5_GDdefcomp(gridID, HE5_HDFE_COMP_DEFLATE, NULL);  
  
status = HE5_GDdeffield(gridID, "Pressure",  
"YDim,XDim",NULL, H5T_NATIVE_FLOAT, HE5_HDFE_NOMERGE);  
  
status = HE5_GDdeffield(gridID, "Opacity", "YDim,XDim",  
NULL, H5T_NATIVE_FLOAT, HE5_HDFE_NOMERGE);
```

```
status = HE5_GDdefield(gridID, "Spectra", "Bands,YDim,XDim",
NULL, H5T_NATIVE_FLOAT, HE5_HDFE_NOMERGE);
```

```
status = HE5_GDdefcomp(gridID, HE5_HDFE_COMP_NONE, NULL);
```

```
status = HE5_GDdefield(gridID, "Temperature", "YDim,XDim",
NULL, H5T_NATIVE_FLOAT, HE5_HDFE_NOMERGE);
```

Note that the HE5_HDFE_NOMERGE parameter will be ignored in the field definitions.

FORTRAN integer function *he5_gddefcomp(gridid, compcode, compparm)*

integer *gridid*

integer *compcode*

integer *compparm*(*)

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
```

```
parameter (HE5_HDFE_COMP_NONE=0)
```

```
parameter (HE5_HDFE_COMP_DEFLATE=4)
```

```
parameter (HE5_HDFE_NOMERGE = 0)
```

```
status = he5_gddefcomp(gridid, HE5_HDFE_COMP_DEFLATE,
compparm)
```

```
status = he5_gddefld(gridid, "Pressure", "YDim,XDim", " ",
HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

```
status = he5_gddefld(gridid, "Opacity", "YDim,XDim",
" ", HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

```
status = he5_gddefld(gridid, "Spectra", "Bands,YDim,XDim",
" ", HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

```
status = he5_gddefcomp(gridid, HE5_HDFE_COMP_NONE, compparm)
```

```
status = he5_gddefld(gridid, "Temperature", "YDim,XDim", "
", HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

Define Compression with Data Tiling

HE5_GDdefcomtile

herr_t HE5_GDdefcomtile(hid_t *gridID*, int *compcode*, int **compparm*, int *tilerank*, const hsize **tiledim*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

compcode IN: Compression method flag

compparm IN: Array of compression parameters

tilerank IN: Rank of a field to compress

tiledim IN: Array of sizes of tile

Purpose Compress the data field

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This function allows the user to set compression for a data field with automatic tiling

Example In this example, we set (DEFLATE) compression for a field that is defined right after this call

```
compcode = 4;
compparm[0] = 6;
status = HE5_GDdefcomtile(gridID, compcode, compparm,
tilerank, tiledim);
```

FORTRAN integer function he5_gddefcomtle(gridid, compcode, compparm, tilerank, tiledim)

integer *gridid*

integer *compcode*

integer *compparm*(*)

integer *tilerank*

integer*4 *tiledim*

The equivalent *FORTRAN* code for the example above is

```
status = he5_gddefcomtle(gridid, compcode, compparm,tilerank,tiledim)
```

Define a New Dimension within a Grid

HE5_GDdefdim

herr_t HE5_GDdefdim(hid_t *gridID*, char **dimname*, hsize_t *dim*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

dimname IN: Name of dimension to be defined

dim IN: The size of the dimension

Note: Merging is not supported in this release of the library. There are three illegal characters for field names: “/”, “;”, “,”

Purpose Defines a new dimension within the grid.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reason for failure is an improper grid id.

Description This routine defines dimensions that are used by the field definition routines (described subsequently) to establish the size of the field.

Example In this example, we define a dimension, *Band*, with size 15.

```
status = HE5_GDdefdim(gridID, "Band", 15);
```

To specify an unlimited dimension which can be used to define an appendable array, the dimension value should be set to zero or equivalently, *H5S_UNLIMITED*:

```
status = HE5_GDdefdim(gridID, "Unlim", H5S_UNLIMITED);
```

FORTTRAN integer function he5_gddefdim(*gridid*, *fieldname*, *dim*)

integer *gridid*

character*(*) *fieldname*

integer*4 *dim*

The equivalent *FORTTRAN* code for the example above is:

```
parameter (H5S_UNLIMITED=-1)
```

```
dim = 15
```

```
status = he5_gddefdim(gridid, "Band", dim)
```

```
status = he5_gddefdim(gridid, "Unlim", H5S_UNLIMITED)
```

Define a New Data Field within a Grid

HE5_GDdefield

herr_t HE5_GDdefield(hid_t *gridID*, const char **fieldname*, char **dimlist*, char **maxdimlist* hid_t *ntype*, int *merge*)

<i>gridID</i>	IN:	Grid ID returned by HE5_GDcreate or HE5_GDattach
<i>fieldname</i>	IN:	Name of field to be defined
<i>dimlist</i>	IN:	The list of data dimensions defining the field
<i>maxdimlist</i>	IN:	The maximum dimensions list defining the field
<i>ntype</i>	IN:	The number type of the data stored in the field
<i>merge</i>	IN:	Merge code (HE5_HDFE-NOMERGE (0) - no merge, HE5_HDFE_AUTOMERGE (1) -merge)

Note: Merging is not supported in this release of the library. There are three illegal characters for field names: “/”, “;”, “,”

Purpose	Defines a new data field within the grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reason for failure is an unknown dimension in the dimension list.
Description	This routine defines data fields to be stored in the grid. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in <i>C</i> order, that is, the last dimension is incremented first.
Example	<p>In this example, we define a grid field, <i>Temperature</i> with dimensions <i>XDim</i> and <i>YDim</i> (as established by the <i>HE5_GDcreate</i> routine) containing 4-byte floating point numbers and a field, <i>Spectra</i>, with dimensions <i>XDim</i>, <i>YDim</i>, and <i>Bands</i>:</p> <pre>status = HE5_GDdefield(gridID, "Temperature", "YDim,XDim", NULL, H5T_NATIVE_FLOAT, 0); status = HE5_GDdefield(gridID, "Spectra", "Bands,YDim,XDim", NULL, H5T_NATIVE_FLOAT, 0);</pre>
FORTTRAN	<pre>integer function he5_gddefld(<i>gridid</i>, <i>fieldname</i>, <i>dimlist</i>, <i>maxdimlist</i>, <i>ntype</i>, <i>merge</i>) integer <i>gridid</i></pre>

character*(*) *fieldname*

character*(*) *dimlist*

character*(*) *maxdimlist*

integer *n* *type, merge*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
```

```
parameter (HE5_HDFE_NOMERGE=0)
```

```
status = he5_gddeffld(gridid, "Temperature", "XDim,YDim", "  
", HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

```
status = he5_gddeffld(gridid, "Spectra", "XDim,YDim,Bands", "  
" ", HE5_HDFE_NATIVE_FLOAT,HE5_HDFE_NOMERGE)
```

The dimensions are entered in *FORTRAN* order with the first dimension incremented first.

Define the Origin of the Grid Data

HE5_GDdeforigin

herr_t HE5_GDdeforigin(hid_t *gridID*, int *origincode*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

origincode IN: Location of the origin of the grid data

Purpose Defines the origin of the grid data

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description The routine is used to define the origin of the grid data. This allows the user to select any corner of the grid as the origin.

Origin Codes:

HE5_HDFE_GD_UL(Default) (0) Upper Left corner of grid

HE5_HDFE_GD_UR (1) Upper Right corner of grid

HE5_HDFE_GD_LL (2) Lower Left corner of grid

HE5_HDFE_GD_LR (3) Lower Right corner of grid

Example In this example we define the origin of the grid to be the Lower Right corner:

```
status = HE5_GDdeforigin(gridID, HE5_HDFE_GD_LR);
```

FORTRAN integer function he5_gddeforg(*gridid*, *origincode*)

integer *gridid*

integer *origincode*

The equivalent *FORTRAN* code for the above example is :

```
parameter (HE5_HDFE_GD_LR=3)
```

```
status = he5_gddeforg(gridid, HE5_HDFE_GD_LR)
```

Define a Pixel Registration within a Grid

HE5_GDdefpixreg

herr_t HE5_GDdefpixreg(hid_t *gridID*, int *pixregcode*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

pixregcode IN: Pixel registration code

Purpose Defines pixel registration within grid cell

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine is used to define whether the pixel center or pixel corner (as defined by the *HE5_GDdeforigin* routine) is used when requesting the location (longitude and latitude) of a given pixel.

Registration Codes:

HE5_HDFE_CENTER (0) (Default) Center of pixel cell

HE5_HDFE_CORNER (1) Corner of a pixel cell

Example In this example, we define the pixel registration to be the corner of the pixel cell:

```
status = HE5_GDdefpixreg(gridID, HE5_HDFE_CORNER);
```

FORTRAN integer function he5_gddefpixreg(*gridid*, *pixregcode*)

integer *gridid*

integer *pixregcode*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_CORNER=1)
```

```
status = he5_gddefpixreg(gridid, HE5_HDFE_CORNER)
```

Define Grid Projection

HE5_GDdefproj

herr_t HE5_GDdefproj(hid_t *gridID*, int *projcode*, int *zonecode*, int *spherecode*,
double *projparm*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

projcode IN: GCTP projection code

zonecode IN: GCTP zone code used by UTM projection

spherecode IN: GCTP spheroid code

projparm IN: GCTP projection parameter array

Purpose Defines projection of grid

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description Defines the GCTP projection and projection parameters of the grid.

Example In this example, we define a Universal Transverse Mercator (UTM) grid bounded by 54 E - 60 E longitude and 20 N - 30 N latitude – UTM zonecode 40, using default spheroid (Clarke 1866), spherecode = 0

```
spherecode = 0;
```

```
zonecode = 40;
```

```
status = HE5_GDdefproj(gridID, HE5_GCTP_UTM, zonecode,  
spherecode, NULL);
```

In this next example we define a Polar Stereographic projection of the Northern Hemisphere (True scale at 90 N, 0 Longitude below pole) using the International 1967 spheroid.

```
spherecode = 3;
```

```
for (i = 0; i < 13; i++) projparm[i] = 0;
```

```
/* Set Long below pole & true scale in DDDMMSS.SSS form */
```

```
projparm[5] = 90000000.00;
```

```
status = HE5_GDdefproj(gridID, HE5_GCTP_PS, NULL,  
spherecode, projparm);
```

Finally we define a Geographic projection. In this case neither the zone code, sphere code or the projection parameters are used.

```
status = HE5_GDdefproj(gridID, HE5_GCTP_GEO, NULL, NULL,  
NULL)
```

FORTTRAN integer function he5_gddefproj(gridid, projcode, zonecode, spherecode,
projparm)

```
integer      gridid  
integer      projcode  
integer      zonecode  
integer      spherecode  
real*8       projparm(*)
```

The equivalent FORTRAN code for the examples above is:

```
parameter (HE5_GCTP_UTM=1)  
spherecode = 0  
zonecode = 40  
status = he5_gddefproj(gridid, HE5_GCTP_UTM, zonecode,  
spherecode, dummy)  
parameter (HE5_GCTP_PS=6)  
spherecode = 6  
do i=1,13  
    projparm(i) = 0  
enddo  
projparm(6) = 90000000.00  
status = he5_gddefproj(gridid, HE5_GCTP_PS, dummy,  
spherecode, projparm)  
parameter (GCTP_GEO=0)  
status = he5_gddefproj(gridid, HE5_GCTP_GEO, dummy, dummy,  
dummy)
```

Note: projcode, zonecode, spherecode and projection parameter information are listed in Section 1.6, GCTP Usage.

Define Tiling Parameters

HE5_GDdeftile

herr_t HE5_GDdeftile(hid_t *gridID*, int *tilecode*, int *tilerank*, const hsize_t **tiledims*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

tilecode IN: Tile code: HE5_HDF_TILE, HE5_HDF_NOTILE (default)

tilerank IN: The number of tile dimensions

tiledims IN: Tile dimensions

Purpose Defines tiling dimensions for subsequent field definitions

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description This routine defines the tiling dimensions for fields defined following this function call, analogous to the procedure for setting the field compression scheme using *HE5_GDdefcomp*. The number of tile dimensions and subsequent field dimensions must be the same and the tile dimensions must be integral divisors of the corresponding field dimensions. A tile dimension set to 0 will be equivalent to 1.

Example We will define four fields in a grid, two two-dimensional fields of the same size with the same tiling, a three-dimensional field with a different tiling scheme, and a fourth with no tiling. We assume that *XDim* is 200 and *YDim* is 300.

```
tiledims[0] = 100;
tiledims[1] = 200;

status = HE5_GDdeftile(gridID, HE5_HDFE_TILE, 2, tiledims);

status = HE5_GDdeffield(gridID, "Pressure", "YDim,XDim",
NULL, H5T_NATIVE_INT, 0);

status = HE5_GDdeffield(gridID, "Temperature", "YDim,XDim",
NULL, H5T_NATIVE_FLOAT, 0);

tiledims[0] = 1;
tiledims[1] = 150;
tiledims[2] = 100;

status = HE5_GDdeftile(gridID, HE5_HDFE_TILE, 3, tiledims);
```

```

status = HE5_GDdeffield(gridID, "Spectra",
" Bands,YDim,XDim", NULL, H5T_NATIVE_FLOAT,
HE5_HDFE_NOMERGE);

status = HE5_GDdeftile(gridID, HE5_HDFE_NOTILE, 0, NULL);

status = HE5_GDdeffield(gridID, "Communities", "YDim,XDim",
NULL, H5T_NATIVE_INT, HE5_HDFE_AUTOMERGE);

```

FORTRAN integer function *he5_gddeftle(gridid, tilecode,tilerank,tiledims)*

```

integer      gridid
integer      tilecode
integer      tilerank
integer*4    tiledims(*)

```

The equivalent *FORTRAN* code for the example above is:

```

parameter (HE5_HDFE_NATIVE_INT=0)
parameter (HE5_HDFE_NATIVE_FLOAT=1)
parameter (HE5_HDFE_NOTILE=0)
parameter (HE5_HDFE_TILE=1)
parameter (HE5_HDFE_NOMERGE = 0)

tiledims(1) = 200
tiledims(2) = 100
tilerank    = 2

status = he5_gddeftle(gridid, HE5_HDFE_TILE,tilerank,
tiledims)

status = he5_gddeffld(gridid, 'Pressure', 'XDim,YDim', " ",
HE5_HDFE_NATIVE_INT, HE5_HDFE_NOMERGE)

status = he5_gddeffld(gridid, 'Temperature', 'XDim,YDim',
" ", HE5_HDFE_NATIVE_FLOAT, HE5_HDFE_NOMERGE)

tiledims[1] = 100
tiledims[2] = 150
tiledims[3] = 1
tilerank    = 3

```

```
status = he5_gddefltle(gridid, HE5_HDFE_TILE, tilerank,  
tiledims)  
  
status = he5_gddeffld(gridid, 'Spectra', 'XDim,YDim,Bands',  
" ", HE5_HDFE_NATIVE_FLOAT, HE5_HDFE_NOMERGE)  
  
tilerank = 2  
  
status = he5_gddefltle(gridid, HE5_HDFE_NOTILE, tilerank,  
tiledims);  
  
status = he5_gddeffld(gridid, 'Communities', 'XDim,YDim', "  
", HE5_HDFE_NATIVE_INT, HE5_HDFE_AUTOMERGE)
```

Define a Time Period of interest

HE5_GDdeftimeperiod

herr_t HE5_GDdeftimeperiod(hid_t *gridID*, hid_t *periodID*, double *starttime*, double *stoptime*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

periodID IN: Period (or region) id from previous subset call

starttime IN: Start time of period

stoptime IN: Stop time of period

Purpose Defines a time period for a grid.

Return value Returns the grid period ID if successful or FAIL (-1) otherwise.

Description This routine defines a time period for a grid. It returns a grid period ID which is used by the *HE5_GDextractperiod* routine to read all the entries of a data field within the time period.. The grid structure must have the *Time* field defined. This routine may be called after *HE5_GDdefboxregion* to provide both geographic and time subsetting . In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) Furthermore it can be called before or after *HE5_GDdefvrtregion* to further refine a region. This routine may also be called “stand-alone” by setting the input id to HE5_HDFE_NOPREVSUB (-1).

Example In this example, we define a time period with a start time of 35232487.2 and a stop time of 36609898.1.

```
starttime = 35232487.2;
```

```
stoptime = 36609898.1;
```

```
periodID = HE5_GDdeftimeperiod(gridID, HE5_HDFE_NOPREVSUB  
starttime, stoptime);
```

If we had previously performed a geographic subset with id, *regionID*, then we could further time subset this region with the call:

```
periodID = HE5_GDdeftimeperiod(gridID, regionID, starttime,  
stoptime);
```

Note that *periodID* will have the same value as *regionID*.

```
FORTRAN integer function he5_gddefmeper(gridid, periodID, starttime, stoptime)
integer      gridid
integer      periodid
real*8       starttime
real*8       stoptime
```

The equivalent *FORTRAN* code for the examples above are:

```
parameter (HE5_HDFE_NOPREVSUB=-1)
starttime = 35232487.2
stoptime  = 36609898.1

periodid = he5_gddefmeper(gridid, HE5_HDFE_NOPREVSUB,
starttime, stoptime)

periodid = he5_gddefmeper(gridid, regionid, starttime,
stoptime)
```

Define a Vertical Subset Region

HE5_GDdefvrtregion

hid_t HE5_GDdefvrtregion(hid_t *gridID*, hid_t *regionID*, char **vertObj*, double *range*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

regionID IN: Region (or period) id from previous subset call

vertObj IN: Dimension or field to subset

range IN: Minimum and maximum range for subset

Purpose Subsets on a **monotonic** field or contiguous elements of a dimension.

Return value Returns the grid region ID if successful or FAIL (-1) otherwise.

Description Whereas the *HE5_GDdefboxregion* routine subsets along the *XDim* and *YDim* dimensions, this routine allows the user to subset along any other dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range(case 2) . In the second case, the field must be one-dimensional and the values must be **monotonic** (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this routine, the second option is restricted to fields with number type: INT, LONG, FLOAT, DOUBLE.) This routine may be called after *HE5_GDdefboxregion* to provide both geographic and “vertical” subsetting . In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the input id to HE5_HDFE_NOPREVSUB (-1).

This routine may be called up to eight times with the same region ID. In this way a region can be subsetted along a number of dimensions.

The *HE5_GDregioninfo* and *HE5_GDextractregion* routines work as before, however the field to be subsetted, (the field specified in the call to *HE5_GDregioninfo* and *HE5_GDextractregion*) must contain the dimension used explicitly in the call to *HE5_GDdefvrtregion* (case 1) or the dimension of the one-dimensional field (case 2).

Example Suppose we have a field called *Pressure* of dimension *Height* (= 10) whose values increase from 100 to 1000. If we desire all the elements with values between 500 and 800, we make the call:

```

range[0] = 500.;
range[1] = 800.;
regionID = HE5_GDdefvrtregion(gridID, HE5_HDFE_NOPREVSUB,
"Pressure", range);

```

The routine determines the elements in the *Height* dimension which correspond to the values of the *Pressure* field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the *Height* dimension, the call would be:

```

range[0] = 2;
range[1] = 5;
regionID = HE5_GDdefvrtregion(gridID, HE5_HDFE_NOPREVSUB,
"DIM:Height", range);

```

The "DIM:" prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field.

If a previous subset region or period was defined with id, *subsetID*, that we wish to refine further with the vertical subsetting defined above we make the call:

```

regionID = HE5_GDdefvrtregion(gridID, subsetID, "Pressure",
range);

```

The return value, *regionID* is set equal to *subsetID*. That is, the subset region is modified rather than a new one created.

In this example, any field to be subsetted must contain the *Height* dimension.

```

FORTRAN integer function he5_gddefvrtreg(gridid, regionid, vertobj, range)
integer      gridid
integer      regionid
character*(*) vertobj
real*8       range(2)

```

The equivalent *FORTRAN* code for the examples above is:

```

parameter (HE5_HDFE_NOPREVSUB=-1)
range(1) = 500.
range(2) = 800.
regionid = he5_gddefvrtreg(gridid, HE5_HDFE_NOPREVSUB,
"Pressure", range)
range(1) = 3      ! Note 1-based element numbers
range(2) = 6
regionid = he5_gddefvrtreg(gridid, HE5_HDFE_NOPREVSUB,
"DIM:Height", range)
regionid = he5_gddefvrtreg(gridid, subsetid, "Pressure",
range)

```

Detach from Grid Structure

HE5_GDdetach

herr_t HE5_GDdetach(hid_t *gridID*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

Purpose Detaches from grid interface.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine should be run before exiting from the grid file for every grid opened by *HE5_GDcreate* or *HE5_GDattach*.

Example In this example, we detach the grid structure, *ExampleGrid*:

```
status = HE5_GDdetach(gridID);
```

FORTRAN integer function he5_gddetach(gridid)

```
integer      gridid
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gddetach(gridid)
```

Retrieve Size of Specified Dimension

HE5_GDdiminfo

hsize_t HE5_GDdiminfo(hid_t *gridID*, char **dimname*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

dimname IN: Dimension name

Purpose Retrieve size of specified dimension.

Return value Size of dimension if successful or FAIL(-1) otherwise. A typical reason for failure is an improper grid id or dimension name.

Description This routine retrieves the size of specified dimension.

Example In this example, we retrieve information about the dimension, "*Bands*":

```
dimsize = HE5_GDdiminfo(gridID, "Bands");
```

The return value, *dimsize*, will be equal to 15

FORTRAN integer*4 function he5_gddiminfo(*gridid*,*dimname*)

integer *gridid*

character*(*) *dimname*

The equivalent *FORTRAN* code for the example above is:

```
dimsize = he5_gddiminfo(gridid, "Bands")
```

Duplicate a Region or Period

HE5_GDdupregion

hid_t HE5_GDdupregion(hid_t *oldregionID*)

oldregionID IN: Region or period ID returned by HE5_GDdefboxregion, HE5_GDdeftimeperiod, or HE5_GDdefvrtregion.

Purpose Duplicates a region.

Return value Returns new region or period ID if successful or FAIL (-1) otherwise.

Description This routine copies the information stored in a current region or period to a new region or period and generates a new id. It is usefully when the user wishes to further subset a region (period) in multiple ways.

Example In this example, we first subset a grid with *HE5_GDdefboxregion*, duplicate the region creating a new region ID, *regionID2*, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = HE5_GDdefboxregion(gridID, cornerlon, cornerlat);
regionID2 = HE5_GDdupregion(regionID);
regionID = HE5_GDdefvrtregion(gridID, regionID, "Pressure",
rangePres);
regionID2 = HE5_GDdefvrtregion(gridID, regionID2,
"Temperature", rangeTemp);
```

FORTRAN integer he5_gddupreg(*oldregionid*)

integer *oldregionid*

The equivalent *FORTRAN* code for the example above is:

```
regionid = he5_gddefboxreg(gridid, cornerlon, cornerlat)
regionid2 = he5_gddupreg(regionid)
regionid = he5_gddefvrtreg(gridid, regionid, 'Pressure',
rangePres)
regionid2 = he5_gddefvrtreg(gridid, regionid2,
'Temperature', rangeTemp)
```

Read a Region of interest from a Field

HE5_GDextractregion

herr_t HE5_GDextractregion(hid_t *gridID*, hid_t *regionID*, const char **fieldname*, void **buffer*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

regionID IN: Region (period) ID returned by HE5_GDdefboxregion (HE5_GDdeftimeperiod)

fieldname IN: Field to subset

buffer OUT: Data Buffer

Purpose Extracts (reads) from subsetted region.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine reads data into the data buffer from a subsetted region as defined by *HE5_GDdefboxregion*.

Example In this example, we extract data from the *Temperature* field from the region defined in *HE5_GDdefboxregion*. We first allocate space for the data buffer. The size of the subsetted region for the field is given by the HE5_GDregioninfo routine.

```
datbuf = (float *)calloc(size, sizeof(float));
status = HE5_GDextractregion(GDdid, regionID, "Temperature",
datbuf);
```

FORTTRAN integer function he5_gdextreg(*gridid*, *regionid*, *fieldname*, *datbuf*)

integer *gridid*

integer *regionid*

character*(*) *fieldname*

<valid type> *buffer*(*)

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_gdextreg(gridid, regionid, "Temperature",
datbuf)
```

Retrieve Information about Data Field in a Grid

HE5_GDfieldinfo

herr_t HE5_GDfieldinfo(hid_t *gridID*, const char **fieldname*, int **rank*, hsize_t *dims*[], H5T_class_t *ntype*[], char **dimlist*, char **maxdimlist*)

<i>gridID</i>	IN: Grid ID returned by HE5_GDcreate or HE5_GDattach
<i>fieldname</i>	IN: Fieldname
<i>rank</i>	OUT: Pointer to rank of the field
<i>dims</i>	OUT: Array containing the dimension sizes of the field
<i>ntype</i>	OUT: Pointer to the numbertype of the field
<i>dimlist</i>	OUT: Dimension list
<i>maxdimlist</i>	OUT: Maximum dimensions allowed for field
Purpose	Retrieve information about a specific geolocation or data field in the grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. A typical reason for failure is the specified field does not exist.
Description	This routine retrieves information on a specific data field.
Example	In this example, we retrieve information about the <i>Spectra</i> data fields: <pre>status = HE5_GDfieldinfo(gridID, "Spectra", &rank, dims, &ntype, dimlist, maxdimlist);</pre> <p>The return parameters will have the following values:</p> <pre>rank=3, ntype=1, dims[3]={ 15,200,120} and dimlist="Bands,YDim,XDim"</pre>

FORTRAN integer function he5_gdfldinfo(*gridid*, *fieldname*, *rank*, *dims*, *ntype*,
dimlist, *maxdimlist*)

integer *gridid*

character*(*) *fieldname*

integer(*) *rank*

integer*4 *dims*(*)

integer *ntype*(*)

character*(*) *dimlist*

character*(*) *maxdimlist*

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdfldinfo(gridid, "Spectra", dims, rank, ntype,  
dimlist, maxdimlist)
```

The return parameters will have the following values:

rank=3, *ntype*=1, *dims*[3]={120,200,15} and

dimlist="XDim,YDim,Bands"

Note that the dimensions array and the dimension list are in *FORTRAN* order.

Get External Data File Information

HE5_GDgetextdata

int HE5_GDgetextdata(hid_t *gridID*, char **fieldname*, size_t *namelength*, char **filelist*, off_t *offset[]*, hsize_t *size[]*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: External field name

namelength OUT: Length of each name entry

filelist OUT: List of file names

offset[] OUT: Array of offsets (in byte) from the beginning of file to the location in file where the data starts

size[] OUT: Array of sizes (in bytes) reserved in the file for the data

Purpose Retrieves information about external data file(s) associated with the data set.

Return value Returns number of external data files if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper grid ID or field name.

Example In this example, we get information about the *ExtData* field:

```
nfiles = HE5_GDgetextdata(gridID, "ExtData", namlen,  
filenames, offset, size);
```

FORTRAN integer function he5_gdgetxdat(*gridid*,*fieldname*,*nlen*,*fllist*,*offset*,*size*)

integer *gridid*

integer *nfiles*

integer*4 *nlen*

integer*4 *offset*(*)

integer*4 *size*(*)

character*(*) *fieldname*

character*(*) *fllist*

The equivalent *FORTRAN* code for the example above is:

```
nfiles = he5_gdgetxdat(gridid, "ExtData", nlen,  
fllist, offset, size)
```

Get Fill Value for Specified Field

HE5_GDgetfillvalue

herr_t HE5_GDgetfillvalue(hid_t *gridID*, const char **fieldname*, void **fillvalue*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Fieldname

fillvalue OUT: Space allocated to store the fill value

Purpose Retrieves fill value for the specified field.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper Grid ID or number type or incorrect fill value.

Description It is assumed the number type of the fill value is the same as the field.

Example In this example, we get the fill value for the *Temperature* field:

```
status = HE5_GDgetfillvalue(gridID, "Temperature",
&tempfill);
```

FORTTRAN integer function he5_gdgetfill(*gridid*,*fieldname*,*fillvalue*)

integer *gridid*

character*(*) *fieldname*

<valid type> *fillvalue*(*)

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_gdgetfill(gridid, "Temperature", tempfill)
```

Get Row/Columns for Specified Longitude/Latitude Pairs

HE5_GDgetpixels

herr_t HE5_GDgetpixels(hid_t *gridID*, long *nLonLat*, double *lonVal[]*, double *latVal[]*, long *pixRow[]*, long *pixCol[]*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach
nLonLat IN: Number of longitude/latitude pairs
lonVal IN: Longitude values in degrees
latVal IN: Latitude values in degrees
pixRow OUT: Pixel Rows
pixCol OUT: Pixel Columns

Purpose Returns the pixel rows and columns for specified longitude/latitude pairs.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine converts longitude/latitude pairs into (0 - based) pixel rows and columns. The origin is the upper left-hand corner of the grid. This routine is the pixel subsetting equivalent of *HE5_GDdefboxregion*.

Example To convert two pairs of longitude/latitude values to rows and columns, make the following call:

```
lonArr[0] = 134.2;  
latArr[0] = -20.8;  
lonArr[1] = 15.8;  
latArr[1] = 84.6;  
  
status = HE5_GDgetpixels(gridID, 2, lonArr, latArr, rowArr,  
colArr);
```

The row and column of the two pairs will be returned in the *rowArr* and *colArr* arrays.

FORTRAN integer function *he5_gdgetpix(gridid, nlonlat, lonval, latval, pixrow, pixcol)*

integer *gridid*

integer*4 *nlonlat*

real*8 *lonval(*)*

real*8 *latval(*)*

integer*4 *pixrow(*)*

integer*4 *pixcol(*)*

The equivalent *FORTRAN* code for the example above is:

```
lonarr(1) = 134.2
```

```
latarr(1) = -20.8
```

```
lonarr(2) = 15.8
```

```
latarr(2) = 84.6
```

```
nlonlat = 2
```

```
status = he5_gdgetpix(gridid, nlonlat, lonarr, latarr,  
rowarr, colarr)
```

Note that the row and columns values will be 1 - based.

Get Field Values for Specified Row/Columns

HE5_GDgetpixvalues

long HE5_GDgetpixvalues(hid_t *gridID*, long *nPixels*, long *pixRow[]*, long *pixCol[]*, const char **fieldname*, void **buffer*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

nPixels IN: Number of pixels

pixRow IN: Pixel Rows

pixCol IN: Pixel Columns

fieldname IN: Field from which to extract data values

buffer OUT: Buffer for data values

Purpose Read field data values for specified pixels.

Return value Returns size of data buffer if successful or FAIL(-1) otherwise.

Description This routine reads data from a data field for the specified pixels. It is the pixel subsetting equivalent of *HE5_GDextractregion*. All entries along the non-geographic dimensions (ie, NOT *XDim* and *YDim*) are returned. If the buffer is set to NULL, no data is returned but the data buffer size can be determined from the function return value.

Example To read values from the *Spectra* field with dimensions, *Bands*, *YDim*, and *XDim*, make the following call:

```
double      *datbuf;

bufsiz = HE5_GDgetpixvalues(gridID, 2, rowArr, colArr,
    "Spectra", NULL);

/* bufsiz will be equal to 2 * NBANDS * 8 where NBANDS is
the value for the Bands dimension */

datbuf = (double *)calloc(bufsiz, sizeof(double));

bufsiz = HE5_GDgetpixvalues(gridID, 2, rowArr, colArr,
    "Spectra", datbuf);
```

FORTRAN integer*4 function he5_gdgetpixval(*gridid*, *npixels*, *pixrow*, *pixcol*,
fieldname, *buffer*)

integer *gridid*

integer*4 *npixels*

integer*4 *bufsiz*

integer*4 *pixrow*(*)

integer*4 *pixcol*(*)

character*(*) *fieldname*

<valid type> *buffer*(*)

The equivalent *FORTRAN* code for the example above is:

```
real*8      datbuf(2,NBANDS)
```

```
npixels = 2
```

```
bufsiz = he5_gdgetpixval(gridid, npixels, rowarr, colarr,  
"Spectra", datbuf)
```

Return Information about a Grid Structure

HE5_GDgridinfo

herr_t HE5_GDgridinfo(hid_t *gridID*, long **xdimsize*, long **ydimsize*, double *upleftpt*[], double *lowrightpt*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

xdimsize OUT: Number of columns in grid

ydimsize OUT: Number of rows in grid

upleftpt OUT: Location, in meters, of upper left corner

lowrightpt OUT: Location, in meters, of lower right corner

Purpose Returns position and size of grid

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description This routine returns the number of rows, columns and the location, in meters, of the upper left and lower right corners of the grid image.

Example In this example, we retrieve information from a previously created grid with a call to *HE5_GDattach*:

```
status = HE5_GDgridinfo(gridID, &xdimsize, &ydimsize,
upleft, lowrgt);
```

FORTTRAN integer function he5_gdgridinfo(*gridid*, *xdimsize*, *ydimsize*, *upleftpt*, *lowrightpt*)

integer *gridid*

integer*4 *xdimsize*

integer*4 *ydimsize*

real*8 *upleftpt*(2)

real*8 *lowrightpt*(2)

The equivalent FORTRAN code for the example above is:

```
status = he5_gdgridinfo(gridid, xdimsize, ydimsize, upleft,
lowrgt)
```

Return Information about a Group Grid Attribute

HE5_GDgrpattrinfo

herr_t HE5_GDgrpattrinfo(hid_t *gridID*, const char **attrname*, H5T_class_t **ntype*, hsize_t **count*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

ntype OUT: Data type class ID of attribute

count OUT: Number of attribute elements

Purpose Returns information about a swath group attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of a swath group attribute.

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_GDgrpattrinfo(gridID, "ScalarFloat", &ntype,
&count);
```

The *ntype* variable will have the value 1 and *count* will have the value 1.

FORTRAN integer function he5_gdgattrinfo(*gridid*, *attrname*, *ntype*, *count*,)

```
integer      gridid
character*(*) attrname
integer      ntype
integer *4   count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = he5_gdgattrinfo(gridid, "ScalarFloat", ntype,
count)
```

Retrieve Information about Grid Attributes

HE5_GDinqattrs

long HE5_GDinqattrs(hid_t *gridID*, char **attrnames*, long **strbufsize*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about attributes defined in grid.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each attribute name separated by commas. If *attrnames* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the attributes defined in a grid structure. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_GDinqattrs(gridID, NULL, strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_GDinqattrs(gridID, attrnames, strbufsize);
```

The variable, *attrlist*, will be set to:

```
"attrOne,attr_2".
```

FORTRAN integer*4 function he5_gdinqattrs(*gridid*,*attrnames*,*strbufsize*)

integer *gridid*

character*(*) *attrnames*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_gdinqattrs(gridid, attrnames, strbufsize)
```

Retrieve Information about Dimensions Defined in Grid

HE5_GDinqdims

int HE5_GDinqdims(hid_t *gridID*, char **dimnames*, hsize_t *dims*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

dimnames OUT: Dimension list (entries separated by commas)

dims OUT: Array containing size of each dimension

Purpose Retrieve information about dimensions defined in grid.

Return value Number of dimension entries found if successful or FAIL(-1) otherwise. A typical reason for failure is an improper grid id.

Description The dimension list is returned as a string with each dimension name separated by commas. Output parameters set to *NULL* will not be returned.

Example To retrieve information about the dimensions, use the following statement:

```
ndim = HE5_GDinqdims(gridID, dimnames, dims);
```

The parameter, *dimnames*, will have the value: "*Xgrid,Ygrid,Bands*"

with *dims*[3]={120,200,15}

FORTRAN integer function he5_gdinqdims(*gridid,dimnames,dims*)

integer *gridid*

character*(*) *dimnames*

integer*4 *dims*(*)

The equivalent *FORTRAN* code for the example above is:

```
ndim = he5_gdinqdims(gridid, dimnames, dims)
```

Retrieve Information about Data Fields Defined in Grid

HE5_GDinqfields

int HE5_GDinqfields(hid_t *gridID*, char **fieldlist*, int *rank*[], H5T_class_t *ntype*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldlist OUT: Listing of data fields (entries separated by commas)

rank OUT: Array containing the rank of each data field

numbertype OUT: Array containing the numbertype of each data field

Purpose Retrieve information about the data fields defined in grid.

Return value Number of data fields found if successful or FAIL(-1) otherwise. A typical reason is an improper grid id.

Description The field list is returned as a string with each data field separated by commas. The *rank* and *numbertype* arrays will have an entry for each field. Output parameters set to *NULL* will not be returned.

Example To retrieve information about the data fields, use the following statement:

```
nfld = HE5_GDinqfields(gridID, fieldlist, rank, numbertype);
```

The parameter, *fieldlist*, will have the value: "*Temperature,Spectra*"

with *rank*[2]={2,3}, *numbertype*[2]={1,1}

FORTRAN integer function he5_gdinqflds(*gridid*, *fieldlist*, *rank*, *numbertype*)

integer *gridid*

character*(*) *fieldlist*

integer *rank*(*)

integer *numbertype*(*)

The equivalent *FORTRAN* code for the example above is:

```
nfld = he5_gdinqflds(gridID, fieldlist, rank, numbertype)
```

The parameter, *fieldlist*, will have the value: "*Spectra,Temperature*"

with *rank*[2]={3,2}, *numbertype*[2]={1,1}

Retrieve Grid Structures Defined in HDF-EOS File

HE5_GDinqgrid

long HE5_GDinqgrid(const char * *filename*, char **gridlist*, long **strbufsize*)

filename IN: HDF-EOS file name

gridlist OUT: Grid list (entries separated by commas)

strbufsize OUT: String length of grid list

Purpose Retrieves number and names of grids defined in HDF-EOS file.

Return value Number of grids found of successful or FAIL (-1) otherwise.

Description The grid list is returned as a string with each grid name separated by commas. If *gridlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. If *strbufsize* is also set to NULL, the routine returns just the number of grids. Note that *strbufsize* does not count the null string terminator.

Example In this example, we retrieve information about the grids defined in an HDF-EOS file, *Grid.he5*. We assume that there are two grids stored, *GridOne* and *Grid_2*:

```
ngrid = HE5_GDinqgrid("Grid.he5", NULL, strbufsize);
```

The parameter, *ngrid*, will have the value 2 and *strbufsize* will have value 16.

```
ngrid = HE5_GDinqgrid("Grid.he5", gridlist, strbufsize);
```

The variable, *gridlist*, will be set to:

"GridOne,Grid_2".

FORTRAN integer*4 function he5_gdinqgrid(*filename*,*gridlist*,*strbufsize*)

character*(*) *filename*

character*(*) *gridlist*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
ngrid = he5_gdinqgrid('Grid.he5', gridlist, strbufsize)
```

Retrieve Information Grid Group Attributes

HE5_GDinqgrpattrs

long HE5_GDinqgrpattrs(hid_t *gridID*, char **attrnames*, long **strbufsize*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about group attributes defined in grid.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each group attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the group attributes defined for the "Data Fields" group. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_GDinqgrpattrs(gridID, NULL, &strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_GDinqgrpattrs(gridID, attrnames, &strbufsize);
```

The variable, *attrlist*, will be set to:

```
"attrOne,attr_2".
```

FORTRAN integer*4 function he5_gdinqgattr(*gridid*, *attrnames*, *strbufsize*)

integer *gridid*

character*(*) *attrnames*

integer*4 *strbufsize*

The equivalent FORTRAN code for the example above is:

```
nattr = he5_gdinqgattr(gridid, attrnames, strbufsize)
```

Retrieve Information Grid Local Attributes

HE5_GDinqlocattr

long HE5_GDinqlocattr(hid_t *gridID*, const char **fieldname*, char **attrnames*, long **strbufsize*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Fieldname to retrieve local attribute information

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about local attributes defined for a field.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each local attribute name separated by commas. If *attrnames* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the local attributes defined for a field "DataField".. We assume that there are two attributes stored, *attrOne* and *attr_2*:

```
nattr = HE5_GDinqlocattr(gridID, "DataField", NULL,
&strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = HE5_GDinqlocattr(gridID, "DataField", attrnames,
&strbufsize);
```

The variable, *attrnames*, will be set to:

```
"attrOne,attr_2".
```

FORTRAN integer*4 function he5_gdinqlattr(*gridid*, *fieldname*, *attrnames*, *strbufsize*)

integer *gridid*

character*(*) *fieldname*

character*(*) *attrnames*

integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = he5_gdinqlattrs(gridid, "DataField", attrnames,  
strbufsize)
```

Perform Bilinear Interpolation on Grid Field

HE5_GDinterpolate

long HE5_GDinterpolate(hid_t *gridID*, long *nValues*, double *lonVal*[], double *latVal*[], const char **fieldname*, double *interpVal*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

nValues IN: Number of interpolation points

lonVal IN: Longitude of interpolation points

latVal IN: Latitude of interpolation points

fieldname OUT: Field from which to interpolate data values

interpVal OUT: Buffer for interpolated data values

Purpose Performs bilinear interpolation on a grid field.

Return value Returns size in bytes of interpolated data values if successful or FAIL(-1) otherwise.

Description This routine performs bilinear interpolation on a grid field. It assumes that the pixel data values are uniformly spaced which is strictly true only for an infinitesimally small region of the globe but is a good approximation for a sufficiently small region. The default position of the pixel value is pixel center, however if the pixel registration has been set to HDFE_CORNER (with the *HE5_GDdefpixreg* routine) then the value is located at one of the four corners (HE5_HDFE_GD_UL, _UR, _LL, _LR) specified by the *HE5_GDdeforigin* routine. All entries along the non-geographic dimensions (ie, NOT *XDim* and *YDim*) are interpolated and all interpolated values are returned as DOUBLE. The data buffer size can be determined by setting the *interpVal* parameter to NULL. The reference for the interpolation algorithm is *Numerical Recipes in C* (2nd ed). (Note for the current version of this routine, the number type of the field to be interpolated is restricted to INT, LONG, FLOAT, DOUBLE.)

Example To interpolate the *Spectra* field at two geographic data points:

```
lonVal[0] = 134.2;
```

```
latVal[0] = -20.8;
```

```
lonVal[1] = 15.8;
```

```

latVal[1] = 84.6;

double      *interpVal;

bufsiz = HE5_GDinterpolate(gridID, 2, lonVal, latVal,
" Spectra", NULL);

/* bufsiz will be equal to 2 * NBANDS * 8 where NBANDS is
the value for the Bands dimension */

interpVal = (double *)calloc(bufsiz, sizeof(double));

bufsiz = HE5_GDinterpolate(gridID, 2, lonVal, latVal,
" Spectra", interpVal);

```

FORTTRAN integer*4 function he5_gdinterpolate(*gridid, ninterp, lonval, latval, fieldname, interpval*)

```

integer      gridid
integer*4    ninterp
real*8      lonval(*)
real*8      latval(*)
character*(*) fieldname
real*8      interpval(*)

```

The equivalent *FORTTRAN* code for the example above is:

```

real*8      interpval(NBANDS, 2)

ninterp = 2

bufsiz = he5_gdinterpolate(gridid, ninterp, lonval, latval,
" Spectra", interpval)

```

Return Information about a Local Grid Attribute

HE5_GDlocattrinfo

herr_t HE5_GDlocattrinfo(hid_t *gridID*, const char **fieldname*, const char **attrname*, H5T_class_t **ntype*, hsize_t **count*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Field name

attrname OUT: Attribute list

numbertype OUT: Data type class ID of attribute

count OUT: Number of attribute elements

Purpose Returns information about a Data Field's local attribute(s)

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of a data field's local attribute(s).

Example In this example, we return information about the *ScalarFloat* attribute.

```
status = HE5_GDlocattrinfo(gridID, "DataField", attrname,
&ntype, &count);
```

The *ntype* variable will have the value 1 and *count* will have the value 1.

FORTRAN integer function he5_gdlatrinfo(*gridid*, *fieldname*, *attrname*, *ntype*,
count)

```
integer      gridid
character(*) fieldname
character(*) attrname
integer      ntype
integer *4   count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = he5_gdlatrinfo(gridid, "DataField", attrname,
ntype, count)
```

Return Number of specified Objects in a Grid

HE5_GDnentries

long HE5_GDnentries(hid_t *gridID*, int *entrycode*, long **strbufsize*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

entrycode IN: Entry code

strbufsize OUT: String buffer size

Purpose Returns number of entries and descriptive string buffer size for a specified entity.

Return value Number of entries if successful or FAIL(-1) otherwise. A typical reason for failure is an improper Grid ID or entry code.

Description This routine can be called before using the inquiry routines in order to determine the sizes of the output arrays and descriptive strings. The string length does not include the NULL terminator.

The entry codes are: HE5_HDFE_NENTDIM (0) - Dimensions

HE5_HDFE_NENTDFLD (4) - Data Fields

Example In this example, we determine the number of data field entries and the size of the field list string.

```
ndims = HE5_GDnentries(gridID, HE5_HDFE_NENTDFLD, &bufsize);
```

FORTRAN integer*4 function he5_gdnentries(*gridid*,*entrycode*, *bufsize*)

integer *gridid*

integer *entrycode*

integer*4 *bufsize*

The equivalent *FORTRAN* code for the example above is:

```
entrycode = 4
```

```
ndims = he5_gdnentries(gridid, entrycode, bufsize)
```

Open HDF-EOS File

HE5_GDopen

hid_t HE5_GDopen(const char **filename*, uintn *access*)

filename IN: Complete path and filename for the file to be opened
access IN: H5F_ACC_RDONLY, H5F_ACC_RDWR or H5F_ACC_TRUNC
Purpose Opens or creates HDF file in order to create, read, or write a grid.
Return value Returns the grid file ID handle(fid) if successful or FAIL(-1) otherwise.
Description This routine creates a new file or opens an existing one, depending on the access parameter.

Access codes:

H5F_ACC_RDONLY	Open for read only. If file does not exist, error
H5F_ACC_RDWR	Open for read/write. If file does not exist, create it
H5F_ACC_TRUNC	If file exists, delete it, then open a new file for read/write

Example In this example, we create a new grid file named, *Grid.he5*. It returns the file handle, *fid*.

```
fid = HE5_GDopen("Grid.he5", H5F_ACC_TRUNC);
```

FORTRAN integer function he5_gdopen(*filename*, *access*)

character*(*) *filename*

integer *access*

The access codes should be defined as parameters:

parameter (HE5_HDFE_RDWR=0)

parameter (HE5_HDFE_RDONLY=1)

parameter (HE5_HDFE_TRUNC=2)

The equivalent *FORTRAN* code for the example above is:

```
fid = he5_gdopen("Grid.he5", HE5_HDFE_TRUNC)
```

Note to users of the SDP Toolkit: Please refer to the *Release 5B SDP Toolkit User Guide for the ECS Project (333-CD-510-001)*, Section 6.2.1.2 for information on how to obtain a file name (referred to as a "physical file handle") from within a PGE. See also Section 9 of this document for code examples.

Return Grid Origin Information

HE5_GDorigininfo

herr_t HE5_GDorigininfo(hid_t *gridID*, int **origincode*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

origincode IN: Origin code

Purpose Retrieve origin code.

Return value Origin code if successful or FAIL (-1) otherwise.

Description This routine retrieves the origin code.

Example In this example, we retrieve the origin code defined in *HE5_GDdeforigin*.

```
status = HE5_GDorigininfo(gridID, &origincode);
```

The return value, *origincode*, will be equal to 3

FORTRAN integer function he5_gdorginfo(*gridid*,*origincode*)

integer *gridid*

integer(*) *origincode*

The equivalent *FORTRAN* code for the above example is :

```
status = he5_gdorginfo(gridid, origincode)
```

Return Pixel Registration Information

HE5_GDpixreginfo

herr_t HE5_GDpixreginfo(hid_t *gridID*, int **pixregcode*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

pixregcode IN: Pixel registration code

Purpose Retrieve pixel registration code.

Return value Pixel registration code if successful or FAIL (-1) otherwise.

Description This routine retrieves the pixel registration code.

Example In this example, we retrieve the pixel registration code defined in *HE5_GDdefpixreg*.

```
status = HE5_GDpixreginfo(gridID, &pixregcode);
```

The return value, *pixregcode*, will be equal to 1

FORTRAN integer function he5_gdpreinfo(*gridid*,*pixregcode*)

integer *gridid*

integer(*) *pixregcode*

The equivalent *FORTRAN* code for the above example is :

```
status = he5_gdpreinfo(gridid, pixregcode)
```

Retrieve Grid Projection Information

HE5_GDprojinfo

herr_t HE5_GDprojinfo(hid_t *gridID*, int **projcode*, int **zonecode*, int **spherecode*, double *projparm*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

projcode OUT: GCTP projection code

zonecode OUT: GCTP zone code used by UTM projection

spherecode OUT: GCTP spheroid code

projparm OUT: GCTP projection parameter array

Purpose Retrieves projection information of grid

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description Retrieves the GCTP projection code, zone code, spheroid code and the projection parameters of the grid

Example In this example, we are retrieving the projection information from a grid attached to with *HE5_GDattached*:

```
status = HE5_GDprojinfo(gridID, &projcode, &zonecode,
&spherecode, projparm);
```

FORTTRAN integer function he5_gdprojinfo(*gridid*, *projcode*, *zonecode*, *spherecode*, *projparm*)

integer(*) *gridid*

integer(*) *projcode*

integer(*) *zonecode*

integer(*) *spherecode*

real*8 *projparm*(*)

The equivalent FORTRAN code for the example above is:

```
status = he5_gdprojinfo(gridid, projcode, zonecode,
spherecode, projparm)
```

Read Grid Attribute

HE5_GDreadattr

herr_t HE5_GDreadattr(hid_t *gridID*, const char **attrname*, void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a grid.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "ScalarFloat":

```
status = HE5_GDreadattr(gridID, "ScalarFloat", &attr_val);
```

FORTTRAN integer function he5_gdrdatr(*gridid*, *attrname*, *datbuf*)

```
integer      gridid
```

```
character*(*) attrname
```

```
<valid type> attrval(*)
```

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_gdrdatr(gridid, "ScalarFloat", attrval)
```

Read Data From a Grid Field

HE5_GDreadfield

herr_t HE5_GDreadfield(hid_t *gridID*, const char **fieldname*, const hssize_t *start*[], const hsize_t *stride*[], const hsize_t *edge*[], void **buffer*)

<i>gridID</i>	IN:	Grid ID returned by HE5_GDcreate or HE5_GDattach
<i>fieldname</i>	IN:	Name of field to read
<i>start</i>	IN:	Array specifying the starting location within each dimension
<i>stride</i>	IN:	Array specifying the number of values to skip along each dimension
<i>edge</i>	IN:	Array specifying the number of values to write along each dimension
<i>buffer</i>	IN:	Buffer to store the data read from the field

Purpose Reads data from a grid field.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are improper Grid ID or unknown fieldname.

Description The values within *start*, *stride*, and *edge* arrays refer to the grid field (input) dimensions. The output data in *buffer* is written to contiguously. The default values for *start* and *stride* are 0 and 1 respectively and are used if these parameters are set to *NULL*. The default values for *edge* are $(dim - start) / stride$ where *dim* refers to the size of the dimension.

Example In this example, we read data from the 10th row (0-based) of the *Temperature* field.

```
float row[120];  
  
hssize_t start[2]={10,1}; hsize_t edge[2]={1,120};  
  
status = HE5_GDreadfield(gridID, "Temperature", start, NULL,  
edge, row);
```

FORTRAN integer function
 he5_gdrdfld(*gridid,fieldname,start,stride,edge,buffer*)
 integer *gridid*
 character*(*) *fieldname*
 integer*4 *start*(*)
 integer*4 *stride*(*)
 integer*4 *edge*(*)
 <valid type> *buffer*(*)

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```
real*4 row(2000)

integer*4 start(2), stride(2), edge(2)

start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1

status = he5_gdrdfld(gridid, "Temperature", start, stride,
edge, row)
```

Read Group Grid Attribute

HE5_GDreadgrpattr

herr_t HE5_GDreadgrpattr(hid_t *gridID*, const char **attrname*, void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a grid.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper grid id or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "ScalarFloat":

```
status = HE5_GDreadgrpattr(gridID, "ScalarFloat",  
&attr_val);
```

FORTTRAN integer function he5_gdrdgattr(*gridid*, *attrname*, *datbuf*)

integer *gridid*

character*(*) *attrname*

<valid type> *attrval*(*)

The equivalent *FORTTRAN* code for the example above is:

```
status = he5_gdrdgattr(gridid, "ScalarFloat", attrval)
```

Read Local Grid Attribute

HE5_GDreadlocattr

herr_t HE5_GDreadlocattr(hid_t *gridID*, const char **fieldname*, const char **attrname*, void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Field name

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads attribute from a grid.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper Grid ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "ScalarFloat":

```
status = HE5_GDreadlocattr(gridID, "DataField",  
"ScalarFloat", &attr_val);
```

FORTRAN integer function he5_gdrdlattr(*gridid*, *fieldname*, *attrname*, *datbuf*)

integer *gridid*

character*(*) *fieldname*

character*(*) *attrname*

<valid type> *attrval*(*)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdrdlattr(gridid, "DataField", "ScalarFloat",  
attrval)
```

Return Information about a Region

HE5_GDregioninfo

herr_t HE5_GDregioninfo(hid_t *gridID*, hid_t *regionID*, const char * *fieldname*, H5T_class_t **ntype*, int **rank*, hsize_t *dims*[], long **size*, double *upleftpt*[], double *lowrightpt*[])

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

regionID IN: Region (period) ID returned by HE5_GDdefboxregion (HE5_GDdeftimeperiod)

fieldname IN: Field to subset

ntype OUT: Number type of field

rank OUT: Rank of field

dims OUT: Dimensions of subset region

size OUT: Size in bytes of subset region

upleftpt OUT: Upper left point of subset region

lowrightpt OUT: Lower right point of subset region

Purpose Retrieves information about the subsetted region.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns information about a subsetted region for a particular field. It is useful when allocating space for a data buffer for the region. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields. The *upleftpt* and *lowrightpt* arrays can be used when creating a new grid from the subsetted region.

Example In this example, we retrieve information about the region defined in *HE5_GDdefboxregion* for the *Temperature* field. We use this to allocate space for data in the subsetted region.

```
status = HE5_GDregioninfo(GDId, regionID, "Temperature",
&ntype, &rank, dims, &size, upleft, lowright);
```

FORTRAN integer function *he5_gdreginfo*(*gridid*, *regionid*, *fieldname*, *ntype*, *rank*,
dims, *size*, *upleftpt*, *lowrightpt*)

integer *gridid*

integer *gridid*

character*(*) *fieldname*

integer *ntype*

integer *rank*

integer*4 *dims*(*)

integer*4 *size*

real*8 *upleftpt*(2)

real*8 *lowrightpt*(2)

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdreginfo(gridid, regid, "Spectra", ntype,  
rank, dims, size, upleftpt, lowrightpt)
```

Set External Data File(s)

HE5_GDsetextdata

herr_t HE5_GDsetextdata(hid_t *gridID*, const char **filelist*, off_t *offset[]*, hsize_t *size[]*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach
filelist IN: List of external file names
offset[] IN: Array of offsets (in byte) from the beginning of file to the location in file where the data starts
size[] IN: Array of sizes (in bytes) reserved in the file for the data

Purpose Sets the external data file(s) associated with the data set.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper grid ID.

Example In this example, we set the *ExtData* field:

```
status = HE5_GDsetextdata(gridID, "ext-1.dat,ext-2.dat,ext-3.dat", offset, size);
```

FORTRAN integer function he5_gdsetxdat(*gridid*,*fllist*,*offset*, *size*)

```
integer      gridid  
integer      status  
integer*4    offset(*)  
integer*4    size(*)  
character*(*) fllist
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_gdsetxdat(gridid,fllist,offset,size)
```

Set Fill Value for a Specified Field

HE5_GDsetfillvalue

herr_t HE5_GDsetfillvalue(hid_t *gridID*, const char **fieldname*, hid_t *ntype*, void **fillvalue*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Fieldname

ntype IN: Data type of fill value

fillvalue IN: Pointer to the fill value to be used

Purpose Sets fill value for the specified field.

NOTE: THIS FUNCTION MUST BE CALLED BEFORE THE FUNCTION CALL TO DEFINE THE FIELD IT IS TO BE APPLIED

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type.

Description The fill value is placed in all elements of the field which have not been explicitly defined.

Example In this example, we set a fill value for the *Temperature* field:

```
tempfill = -999.0;
status = HE5_GDsetfillvalue(gridID, "Temperature", ntype,
&tempfill);
```

FORTRAN integer function
he5_gdsetfill(*gridid*,*fieldname*,*ntype*,*fillvalue*)

integer*4 *gridid*

character*(*) *fieldname*

integer *ntype*

<valid type> *fillvalue*(*)

The equivalent *FORTRAN* code for the example above is:

```
fillvalue = -999.0
status = he5_gdsetfill(gridid, "Temperature", ntype,
fillvalue)
```

Write/Update Grid Attribute

HE5_GDwriteattr

herr_t HE5_GDwriteattr(hid_t *gridID*, const char **attrname*, hid_t *ntype*, hsize_t *count*[], void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

ntype IN: Number type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates attribute in a grid.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.

Example In this example. we write a floating point number with the name "ScalarFloat" and the value 3.14:

```
attr_val = 3.14;
```

```
count[0] = 1;
```

```
status=HE5_GDwriteattr(gridid, "ScalarFloat", H5T_NATIVE_FLOAT  
, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;
```

```
status=HE5_GDwriteattr(gridid, "ScalarFloat", H5T_NATIVE_FLOAT  
, count, &attr_val);
```

FORTRAN integer function `he5_gdwrattr(gridid, attrname,`
 `ntype, count, datbuf)`

 integer `gridid`
 character*(*) `attrname`
 integer `ntype`
 integer*4 `count(*)`
 <valid type> `attrval(*)`

The equivalent *FORTRAN* code for the first example above is:

```

parameter (HE5_HDFE_NATIVE_FLOAT=1)

attrval = 3.14

count(1)= 1

status=he5_gdwrattr(gridid,"ScalarFloat",HE5_HDFE_NATIVE_FLO
AT, count, attrval)

```

Write Data to a Grid Field

HE5_GDwritefield

herr_t HE5_GDwritefield(hid_t *gridID*, const char *fieldname*, const hssize_t *start*[], const hssize_t *stride*[], const hssize_t *edge*[], void *data*)

<i>gridID</i>	IN: Grid ID returned by HE5_GDcreate or HE5_GDattach
<i>fieldname</i>	IN: Name of field to write
<i>start</i>	IN: Array specifying the starting location within each dimension (0-based)
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to write along each dimension
<i>data</i>	IN: Values to be written to the field
Purpose	Writes data to a grid field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	The values within <i>start</i> , <i>stride</i> , and <i>edge</i> arrays refer to the grid field (output) dimensions. The input data in the <i>data</i> buffer is read from contiguously. The default values for <i>start</i> and <i>stride</i> are 0 and 1 respectively and are used if these parameters are set to <i>NULL</i> . The default values for <i>edge</i> are $(dim - start) / stride$ where <i>dim</i> refers to the size of the dimension. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines. If this is not possible due to, for example, memory limitations, then the user should consider tiling. See <i>HE5_GDdefile</i> for further information.

Example In this example, we write data to the *Temperature* field.

```
float temperature [200][120];

/* Define elements of temperature array */

status = HE5_GDwritefield(gridID, "Temperature", NULL, NULL,
                          NULL, temperature);

We now update Row 10 (0 - based) in this field:
float newrow[2000];

hssize_t start[2]={0,10}; hssize_t edge[2]={2000,1};
```

```

/* Define elements of newrow array */
status = HE5_GDwritefield(gridID, "Temperature", start, NULL,
    edge, newrow);
FORTRAN integer function he5_gdwrfld(gridid,fieldname,start,stride,edge,data)
integer      gridid
character*(*) fieldname
integer*4    start(*)
integer*4    stride(*)
integer*4    edge(*)
<valid type> data(*)

```

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```

real*4 temperature(2000,1000)
integer*4 start(2), stride(2), edge(2)
start(1) = 0
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1000
status = he5_gdwrfld(gridid, "Temperature", start, stride,
    edge, temperature)

```

We now update Row 10 (0 - based) in this field:

```

real*4 newrow(2000)
integer*4 start(2), stride(2), edge(2)
start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1
status = he5_gdwrfld(gridid, "Temperature", start, stride,
    edge, newrow)

```

Write Field Metadata for an Existing Field not Defined with the Grid API

HE5_GDwritefieldmeta

herr_t HE5_GDwritefieldmeta(hid_t *gridID*, const char **fieldname*, char **dimlist*, int *ntype*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Name of field that metadata information is to be written

dimlist IN: Dimension list of field

ntype IN: Number type of data in field

Purpose Writes field metadata for an existing grid field not defined with the Grid API

Return Value Returns SUCCEED(0) if successful or FAIL(-1) otherwise

Description This routine writes the field metadata for a grid field not defined by the Grid API

Example

```
status = HE5_GDwritefieldmeta(gridID, "ExternField",
"Ydim,Xdim", HE5_HDFE_NATIVE_FLOAT);
```

FORTRAN integer function he5_gdwmeta(gridid, fieldname, dimlist, ntype)

integer *gridid*

character*(*) *fieldname*

character*(*) *dimlist*

integer *ntype*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
```

```
status = he5_gdwmeta(gridid, "ExternField", "Xdim,Ydim",
HE5_HDFE_NATIVE_FLOAT)
```

Write/Update Group Grid Attribute

HE5_GDwritegrpattr

herr_t HE5_GDwritegrpattr(hid_t *gridID*, const char **attrname*, hid_t *ntype*,
hsize_t *count*[], void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

attrname IN: Attribute name

ntype IN: Data type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates group attribute in a grid.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper grid id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call. The attribute is linked to the "Data Fields" group in the swath file.

Example In this example, we write a floating point number with the name "ScalarFloat" and the value 3.14:

```
count[0] = 1;

attr_val = 3.14;

status = HE5_GDwritegrpattr(gridid, "ScalarFloat",
H5T_NATIVE_FLOAT, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;

status = HE5_GDwritegrpattr(gridid, "ScalarFloat",
H5T_NATIVE_FLOAT, count, &attr_val);
```

FORTRAN integer function he5_gdwrgattr(*gridid*, *attrname*, *ntype*, *count*, *datbuf*)
integer *gridid*
character*(*) *attrname*
integer *ntype*
integer*4 *count*(*)
<valid type> *attrval*(*)

The equivalent *FORTRAN* code for the first example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)  
attrval = 3.14  
count(1) = 1  
status = he5_gdwrgattr(gridid, "ScalarFloat",  
HE5_HDFE_NATIVE_FLOAT,count, attrval)
```

Write/Update Local Grid Attribute

HE5_GDwritelocattr

herr_t HE5_GDwritelocattr(hid_t *gridID*, const char **fieldname*, const char **attrname*, hid_t *ntype*, hsize_t *count*[], void **datbuf*)

gridID IN: Grid ID returned by HE5_GDcreate or HE5_GDattach

fieldname IN: Field name

attrname IN: Attribute name

ntype IN: Data type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates group attribute in a grid.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper grid id or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call. The attribute is linked to a particular "Data Field" in the grid file.

Example In this example, we write a floating point number with the name "ScalarFloat" and the value 3.14:

```
count[0] = 1;
attr_val = 3.14;
status = HE5_GDwritelocattr(gridid, "DataField",
"ScalarFloat", H5T_NATIVE_FLOAT, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;
status = HE5_GDwritelocattr(gridid, "DataField",
"ScalarFloat", H5T_NATIVE_FLOAT, count, &attr_val);
```

FORTRAN integer function `he5_gdwrlattr(gridid, fieldname, attrname, ntype, count, datbuf)`

integer `gridid`

character*(*) `fieldname`

character*(*) `attrname`

integer*4 `count(*)`

<valid type> `attrval(*)`

The equivalent *FORTRAN* code for the first example above is:

```
parameter (HE5_HDFE_NATIVE_FLOAT=1)
attrval = 3.14
count(1) = 1
status = he5_gdwrlattr(gridid, "DataField", "ScalarFloat",
HE5_HDFE_NATIVE_FLOAT, count, attrval)
```

2.1.4 HDF-EOS Utility Routines

This section contains an alphabetical list of the utility functions. The functions are alphabetized on their C-language names.

Convert Among Angular Units

HE5_EHconvAng

double HE5_EHconvAng(double *inAngle*, int *code*)

inAngle IN: Input angle

code IN: Conversion code

Purpose Convert among various angular units.

Return value Returns angle in desired units if successful or FAIL (-1) otherwise.

Description This routine converts angles between three units, decimal degrees, radians, and packed degrees-minutes-seconds. In the later unit, an angle is expressed as a integral number of degrees and minutes and a float point value of seconds packed as a single double number as follows: DDDMMMSS.SS. The six conversion codes are: HE5_HDFE_RAD_DEG (0), HE5_HDFE_DEG_RAD (1), HE5_HDFE_DMS_DEG (2), HE5_HDFE_DEG_DMS (3), HE5_HDFE_RAD_DMS (0), and HE5_HDFE_DMS_RAD (1), where the first three letter code (RAD - radians, DEG - decimal degrees, DMS - packed degrees-minutes-seconds) corresponds to the input angle and the second to the desired output angular unit.

Example To convert 27.5 degrees to packed format:

```
inAng = 27.5;
```

```
outAng = HE5_EHconvAng(inAng, HDFE_DEG_DMS);
```

“outAng” will contain the value: 27030000.00.

FORTRAN real*8 function he5_ehconvang(*inangle*,*code*)

```
real*8      inangle
```

```
integer     code
```

The equivalent *FORTRAN* code for the example above is:

```
inangle = 27.5
```

```
code = 3
```

```
outangle = he5_ehconvang(inangle, code)
```

Get HDF-EOS Version String

HE5_EHgetversion

herr_t HE5_EHgetversion(hid_t *fid*, char **version*)

fid IN: File ID returned by *HE5_SWopen*, *HE5_GDopen*, or *HE5_PTopen*.

version OUT: HDF-EOS version string

Purpose Get HDF-EOS version string.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine returns the HDF-EOS version string of an HDF-EOS file. This designates the version of HFD-EOS that was used to create the file. This string if of the form: "HDFEOS_V*maj.min*" where *maj* is the major version and *min* is the minor version.

.

Example To get the HDF-EOS version (assumed to be 5.1.2) used to create the HDF-EOS file: "Swath.he5":

```
char version[16];  
fid = HE5_SWopen("Swath.he5", H5F_ACC_RDONLY);  
status = HE5_EHgetversion(fid, version);  
"version" will contain the string: "HDFEOS_5.1.2".
```

FORTRAN integer function he5_ehgetver(*fid*,*version*)

```
integer      fid  
character*(*) version  
integer      HE5_HDFE_RDONLY  
parameter    (HE5_HDFE_RDONLY=1)
```

The equivalent *FORTRAN* code for the example above is:

```
character*16 version  
  
fid = he5_swopen("Swath.he5",HE5_HDFE_RDONLY)  
  
status = he5_ehgetver(fid, version)
```

Return Information about Global File Attribute

HE5_EHglbatrinfo

herr_t HE5_EHglbatrinfo(hid_t *fileID*, const char **attrname*, H5T_class_t **ntype*, hsize_t **count*)

fileID IN: HDF-EOS file ID returned by HE5_SWopen/HE5_GDopen/HE5_PTopen

attrname IN: Attribute name

numbertype OUT: Data type class ID of attribute

count OUT: Number of attribute elements

Purpose Returns information about Global File attribute

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine returns number type and number of elements (count) of Global File attribute.

Example In this example, we return information about the *FloatAttr* attribute.

```
status = HE5_EHglbatrinfo(fileID, "FloatAttr", &nt, &count);
```

The *nt* variable will have the value 1 and *count* will have the value 1.

FORTRAN integer function he5_ehglatinf(*fileid*, *attrname*, *ntype*, *count*,)
integer *fileid*
character*(*) *attrname*
integer *ntype*
integer *4 *count*

The equivalent *FORTRAN* code for the first example above is:

```
status = he5_ehglatinf(fileid, "FloatAttr",nt,count)
```

Get HDF-EOS File IDs

HE5_EHidinfo

herr_t HE5_EHidinfo(hid_t *fid*, hid_t **HDFfid*, hid_t **gid*)

fid IN: File ID returned by *HE5_SWopen*, *HE5_GDopen*, or *HE5_PTopen*.

HDFfid OUT: HDF-EOS file ID (returned by *HE5_EHopen*)

gid OUT: "HDFEOS" group ID

Purpose Get HDF-EOS file IDs.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This is a wrapper around *HE5_EHchkfid* () and it returns the HDF file IDs to the HDF-EOS file ID returned by *HE5_SWopen*, *HE5_GDopen*, or *HE5_PTopen*. These ids can then be used to create or access HDF5 structures such as groups, attributes, datasets within an HDF-EOS file.

Retrieve Information about Global File Attributes

HE5_EHinqglbattr

long HE5_EHinqglbattr(hid_t *fileID*, char **attrnames*, long **strbufsize*)

fileID IN: HDF-EOS file ID returned by
HE5_SWopen/HE5_GDopen/HE5_PTOpen

attrnames OUT: Attribute list (entries separated by commas)

strbufsize OUT: String length of attribute list

Purpose Retrieve information about Global attributes defined in file.

Return value Number of attributes found if successful or FAIL (-1) otherwise.

Description The attribute list is returned as a string with each group attribute name separated by commas. If *attrlist* is set to NULL, then the routine will return just the string buffer size, *strbufsize*. This variable does not count the null string terminator.

Example In this example, we retrieve information about the Global attributes defined for the "swath.he5" file (with the file ID *fileID*). We assume that there are two attributes stored, *GlobAttr_1* and *GlobAttr_2*:

```
nattr = HE5_EHinqglbattr(fileID, NULL, &strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 21.

```
nattr = HE5_EHinqglbattr(fileID, attrnames, &strbufsize);
```

The variable, *attrnames*, will be set to:

```
"GlobAttr_1,GlobAttr_2".
```

FORTRAN integer*4 function he5_ehinqglatts(*fileid*, *attrnames*, *strbufsize*)

integer *fileid*

character*(*) *attrnames*

integer*4 *strbufsize*

integer*4 *nattr*

The equivalent FORTRAN code for the example above is:

```
nattr = he5_ehinqglatts(fileid, attrnames, strbufsize)
```

Read Global File Attribute

HE5_EHreadglbattr

herr_t HE5_EHreadglbattr(hid_t *fileID*, const char **attrname*, void **datbuf*)

fileID IN: HDF-EOS file ID returned by
HE5_SWopen/HE5_GDopen/HE5_PTopen

attrname IN: Attribute name

datbuf OUT: Buffer allocated to hold attribute values

Purpose Reads global attribute from a file.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper file ID or number type or incorrect attribute name.

Description The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.

Example In this example, we read a floating point attribute with the name "FloatAttr":

```
status = HE5_EHreadglbattr(fileID, "FloatAttr", &data);
```

FORTRAN integer function he5_ehrdglatt(*fileid*,*attrname*,*datbuf*)

```
integer      fileid
```

```
character*(*) attrname
```

```
<valid type> datbuf(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = he5_ehrdglatt(fileid, "FloatAttr", datbuf)
```

Write/Update Global File Attribute

HE5_EHwriteglbattr

herr_t HE5_EHwriteglbattr(hid_t *fileID*, const char **attrname*, hid_t *ntype*,
hsize_t *count*[], void **datbuf*)

fileID IN: HDF-EOS file ID returned by
HE5_SWopen/HE5_GDopen/HE5_PTopen

attrname IN: Attribute name

ntype IN: Data type of attribute

count IN: Number of values to store in attribute

datbuf IN: Attribute values

Purpose Writes/Updates Global attribute in HDF-EOS file.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper file ID or number type.

Description If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call. The attribute is linked to the "ADDITIONAL/FILE ATTRIBUTES" group in the HDF-EOS file.

Example In this example, we write a single precision (32 bit) floating point number with the name "FloatAttr" and the value 3.14:

```
count[0] = 1;  
  
attr_val = 3.14;  
  
status = HE5_EHwriteglbattr(fileid, "FloatAttr",  
H5T_NATIVE_FLOAT, count, &attr_val);
```

We can update this value by simply calling the routine again with the new value:

```
attr_val = 3.14159;  
  
status = HE5_EHwriteglbattr(fileid, "FloatAttr",  
H5T_NATIVE_FLOAT, count, &attr_val);
```

FORTRAN integer function `he5_ehwrglbattr(fid, attrname, ntype, count, buffer)`
integer `fid, status, ntype`
character `*(*) attrname`
integer*4 `count`
<valid type> `buffer(*)`
integer `HE5_HDFE_NATIVE_FLOAT`
parameter `(HE5_HDFE_NATIVE_FLOAT=1)`

The equivalent *FORTRAN* code for the example above is:

```
count = 1  
  
status = he5_ptwrglbattr(fid, "FloatAttr",  
HE5_HDFE_NATIVE_FLOAT, count, buffer)
```

This page intentionally left blank.

Abbreviations and Acronyms

AI&T	Algorithm Integration & Test
AIRS	Atmospheric Infrared Sounder
API	application program interface
ASTER	Advanced Spaceborne Thermal Emission and Reflection Radiometer
CCSDS	Consultative Committee on Space Data Systems
CDRL	Contract Data Requirements List
CDS	CCSDS day segmented time code
CERES	Clouds and Earth Radiant Energy System
CM	configuration management
COTS	commercial off-the-shelf software
CUC	constant and unit conversions
CUC	CCSDS unsegmented time code
DAAC	distributed active archive center
DBMS	database management system
DCE	distributed computing environment
DCW	Digital Chart of the World
DEM	digital elevation model
DTM	digital terrain model
ECR	Earth centered rotating
ECS	EOSDIS Core System
EDC	Earth Resources Observation Systems (EROS) Data Center
EDHS	ECS Data Handling System
EDOS	EOSDIS Data and Operations System
EOS	Earth Observing System
EOSAM	EOS AM Project (morning spacecraft series)
EOSDIS	Earth Observing System Data and Information System
EOSPM	EOS PM Project (afternoon spacecraft series)

ESDIS	Earth Science Data and Information System (GSFC Code 505)
FDF	flight dynamics facility
FOV	field of view
ftp	file transfer protocol
GCT	geo-coordinate transformation
GCTP	general cartographic transformation package
GD	grid
GPS	Global Positioning System
GSFC	Goddard Space Flight Center
HDF	hierarchical data format
HITC	Hughes Information Technology Corporation
http	hypertext transport protocol
I&T	integration & test
ICD	interface control document
IDL	interactive data language
IP	Internet protocol
IWG	Investigator Working Group
JPL	Jet Propulsion Laboratory
LaRC	Langley Research Center
LIS	Lightening Imaging Sensor
M&O	maintenance and operations
MCF	metadata configuration file
MET	metadata
MODIS	Moderate-Resolution Imaging Spectroradiometer
MSFC	Marshall Space Flight Center
NASA	National Aeronautics and Space Administration
NCSA	National Center for Supercomputer Applications
netCDF	network common data format
NGDC	National Geophysical Data Center
NMC	National Meteorological Center (NOAA)

ODL	object description language
PC	process control
PCF	process control file
PDPS	planning & data production system
PGE	product generation executive (formerly product generation executable)
POSIX	Portable Operating System Interface for Computer Environments
PT	point
QA	quality assurance
RDBMS	relational data base management system
RPC	remote procedure call
RRDB	recommended requirements database
SCF	Science Computing Facility
SDP	science data production
SDPF	science data processing facility
SGI	Silicon Graphics Incorporated
SMF	status message file
SMP	Symmetric Multi-Processing
SOM	Space Oblique Mercator
SPSO	Science Processing Support Office
SSM/I	Special Sensor for Microwave/Imaging
SW	swath
TAI	International Atomic Time
TBD	to be determined
TDRSS	Tracking and Data Relay Satellite System
TRMM	Tropical Rainfall Measuring Mission (joint US – Japan)
UARS	Upper Atmosphere Research Satellite
UCAR	University Corporation for Atmospheric Research
URL	universal reference locator
USNO	United States Naval Observatory
UT	universal time

UTC	Coordinated Universal Time
UTCf	universal time correlation factor
UTM	universal transverse mercator
VPF	vector product format
WWW	World Wide Web